

**Language:** [en][\[cs\]](#) [\[de\]](#) [\[es\]](#) [\[fr\]](#)[\[id\]](#) [\[ja\]](#) [\[ko\]](#) [\[pl\]](#)[\[pt\]](#) [\[zh-cn\]](#) [\[zh-tw\]](#)

## Other Documents

[Upgrade-MiniFAQ](#)[Ports and Packages](#)[Port Testing Guide](#)[Updating via AnonCVS](#)[Stable](#)[CVSup](#)[Manual pages](#)[Bug Reporting](#)[Mail lists](#)[PF User's Guide](#)

## PDF files

[OpenBSD FAQ](#)[PF FAQ](#)

## Text files

[OpenBSD FAQ](#)[PF FAQ](#)

## Back to OpenBSD



# OpenBSD

## Documentation and Frequently Asked Questions

[Commonly Encountered Issues](#)[Recent updates](#)

This FAQ is supplemental documentation to the man pages, available both in the installed system and [online](#). The FAQ covers the active release of OpenBSD, currently v3.3. Note that the development version (-current) of OpenBSD is *not* covered by this FAQ.

The FAQ in PDF and plain text form is available in the `pub/OpenBSD/doc` directory from the [FTP mirrors](#), along with other documents.

### 1 - Introduction to OpenBSD

- [1.1 - What is OpenBSD?](#)
- [1.2 - On what systems does OpenBSD run?](#)
- [1.3 - Is OpenBSD really free?](#)
- [1.4 - Why might I want to use OpenBSD?](#)
- [1.5 - How can I help support OpenBSD?](#)
- [1.6 - Who maintains OpenBSD?](#)
- [1.7 - When is the next release of OpenBSD?](#)
- [1.8 - What is included with OpenBSD?](#)

### 2 - Other OpenBSD Information Resources

- [2.1 - Web Pages](#)
- [2.2 - Mailing Lists](#)
- [2.3 - Manual Pages](#)
- [2.4 - Reporting Bugs](#)

### 3 - Obtaining OpenBSD

- [3.1 - Buying an OpenBSD CD](#)
- [3.2 - Buying OpenBSD T-Shirts](#)
- [3.3 - Does OpenBSD provide an ISO image for download?](#)
- [3.4 - Downloading via FTP or AFS](#)
- [3.5 - Obtaining Current Source Code](#)

## [4 - OpenBSD 3.3 Installation Guide](#)

- [4.1 - Overview of the OpenBSD installation procedure.](#)
- [4.2 - Preinstallation checklist](#)
- [4.3 - Creating bootable OpenBSD install media](#)
- [4.4 - Booting OpenBSD install media](#)
- [4.5 - Performing an install](#)
- [4.6 - What files are needed for Installation?](#)
- [4.7 - How much space do I need for an OpenBSD installation?](#)
- [4.8 - Multibooting OpenBSD](#)
- [4.9 - Sending your dmesg to dmesg@openbsd.org after the install](#)
- [4.10 - Adding a file set after install](#)
- [4.11 - What is 'bsd.rd'?](#)
- [4.12 - Common installation problems](#)
- [4.13 - Customizing the install process](#)
- [4.14 - How can I install a number of similar systems?](#)
- [4.15 - How can I get a dmesg\(8\) to report an install problem?](#)

## [5 - Building the System from Source](#)

- [5.1 - OpenBSD Flavors](#)
- [5.2 - Why do I need a custom kernel?](#)
- [5.3 - Kernel configuration Options](#)
- [5.4 - Building your own kernel](#)
- [5.5 - Boot-time configuration](#)
- [5.6 - Getting more verbose output during boot](#)
- [5.7 - Using config\(8\) to change your kernel binary](#)
- [5.8 - Common Problems when Compiling and Building](#)

## [6 - Networking](#)

- [6.0.1 - Before we go any further](#)
- [6.1 - Initial network setup](#)
- [6.2 - Packet Filter \(PF\)](#)
- [6.4 - Dynamic Host Configuration Protocol](#)
- [6.5 - Point to Point Protocol](#)
- [6.6 - Tuning networking parameters](#)
- [6.7 - Using NFS](#)
- [6.9 - Setting up a PPTP connection in OpenBSD](#)
- [6.10 - Setting up a bridge with OpenBSD](#)

## [7 - Keyboard and Display Controls](#)

- [7.1 - How do I remap the keyboard? \(wscons\)](#)
- [7.2 - Is there gpm or the like in OpenBSD?](#)
- [7.3 - How do I clear the console each time a user logs out?](#)
- [7.4 - Accessing the console scrollbar buffer. \(alpha/macppc/i386\)](#)
- [7.5 - How do I switch consoles? \(i386\)](#)

- [7.6 - How can I use a console resolution of 80x50? \(i386\)](#)
- [7.7 - How do I use a serial console?](#)
- [7.8 - How do I blank my console? \(wscons\)](#)

## 8 - General Questions

- [8.1 - I forgot my root password... What do I do!](#)
- [8.2 - X won't start, I get lots of error messages](#)
- [8.3 - What is CVS, and how do I use it?](#)
- [8.4 - What is the ports tree?](#)
- [8.5 - What are packages?](#)
- [8.6 - Should I use Ports or Packages?](#)
- [8.8 - Is there any way to use my floppy drive if it's not attached during boot?](#)
- [8.9 - OpenBSD Bootloader \(\*i386 specific\*\)](#)
- [8.10 - Using S/Key on your OpenBSD system](#)
- [8.12 - Does OpenBSD support SMP?](#)
- [8.13 - I sometimes get Input/output error when trying to use my tty devices](#)
- [8.14 - What web browsers are available for OpenBSD?](#)
- [8.15 - How do I use the mg editor?](#)
- [8.16 - Ksh does not appear to read my .profile!](#)
- [8.17 - Why does my /etc/motd file get written over when I modified it?](#)
- [8.18 - Why does www.openbsd.org run on Solaris?](#)
- [8.19 - I'm having problems with PCI devices being detected](#)
- [8.20 - Antialiased and TrueType fonts in XFree86](#)
- [8.21 - Does OpenBSD support any journaling filesystems?](#)
- [8.22 - Reverse DNS or Why is it taking so long for me to log in?](#)
- [8.23 - Why do the OpenBSD web pages not conform to HTML4/XHTML?](#)
- [8.24 - Why is my clock off by twenty-some seconds?](#)

## 9 - Migrating from Linux

- [9.1 - Tips for Linux \(and other free Unix-like OS\) users](#)
- [9.2 - Dual boot of Linux and OpenBSD](#)
- [9.3 - Converting your Linux \(or other System-7 style\) password file to BSD-style.](#)
- [9.4 - Getting OpenBSD and Linux to interact](#)

## 10 - System Management

- [10.1 - When I try to su to root it says that I'm in the wrong group](#)
- [10.2 - How do I duplicate a filesystem?](#)
- [10.3 - How do I start daemons with the system? \(Overview of rc\(8\)\)](#)
- [10.4 - Why do users get relaying access denied when they are remotely sending mail through my OpenBSD system?](#)
- [10.5 - I've set up POP, but I get errors when accessing my mail through POP. What can I do?](#)
- [10.6 - Why does Sendmail ignore /etc/hosts file?](#)
- [10.7 - Setting up a Secure HTTP Server using SSL\(8\)](#)
- [10.8 - I made changes to /etc/passwd with vi\(1\), but the changes didn't seem to](#)

take place. Why?

- [10.9 - How do I add a user? or delete a user?](#)
- [10.10 - How do I create a ftp-only account?](#)
- [10.11 - Setting up user disk quotas](#)
- [10.12 - Setting up KerberosV Clients and Servers](#)
- [10.13 - Setting up an Anonymous FTP Server](#)
- [10.14 - Confining users to their home dir's in ftpd\(8\).](#)
- [10.15 - Applying patches in OpenBSD.](#)
- [10.16 - Tell me about chroot\(\) Apache?](#)
- [10.17 - I don't like the standard root shell!](#)
- [10.18 - What else can I do with ksh?](#)

## **11 - Performance Tuning**

- [11.1 - Networking](#)
- [11.2 - Disk I/O](#)
- [11.4 - Hardware Choices](#)
- [11.5 - Why aren't we using async mounts?](#)
- [11.6 - Tuning your monitor resolution under XFree86](#)

## **12 - Platform-Specific Questions**

- [12.1 - General hardware notes](#)
- [12.2 - DEC Alpha](#)
- [12.3 - HP 9000 series 300, 400](#)
- [12.4 - HPPA](#)
- [12.5 - i386](#)
- [12.6 - Mac68k](#)
- [12.7 - MacPPC](#)
- [12.8 - MVME68k](#)
- [12.9 - SPARC](#)
- [12.10 - UltraSPARC](#)
- [12.11 - DEC VAX](#)

## **14 - Disk Setup**

- [14.1 - Using OpenBSD's disklabel](#)
- [14.2 - Using OpenBSD's fdisk](#)
- [14.3 - Adding extra disks in OpenBSD](#)
- [14.4 - How to swap to a file](#)
- [14.5 - Soft Updates](#)
- [14.7 - What are the issues regarding large drives with OpenBSD? -i386 specific](#)
- [14.8 - Installing Bootblocks - i386 specific](#)
- [14.9 - Preparing for disaster: Backing up and Restoring from tape.](#)
- [14.10 - Mounting disk images in OpenBSD](#)
- [14.11 - Help! I'm getting errors with PCIIDE!](#)
- [14.13 - RAID options with OpenBSD](#)

## PF User's Guide

- [Configuration](#)
    - [Lists and Macros](#)
    - [Tables](#)
    - [Options](#)
    - [Scrub](#)
    - [Queueing](#)
    - [Network Address Translation](#)
    - [Traffic Redirection](#)
    - [Packet Filtering](#)
  - [Logging](#)
  - [Anchors and Named \(Sub\) Rulesets](#)
  - [Shortcuts for Creating Rulesets](#)
  - [Address Pools and Load Balancing](#)
  - [Performance](#)
  - [Issues with FTP](#)
  - [Authpf: User Shell for Authenticating Gateways](#)
  - [Example: Firewall for Home or Small Office](#)
- 

## Commonly Encountered Issues

- [Common Installation Problems](#)
  - [Tell me about chroot\(\) Apache?](#)
  - [How do I upgrade my system?](#)
  - [RAID Options.](#)
  - [Packet Filter](#)
  - [Should I use Ports or Packages?](#)
  - [How do I set up a multi-boot system?](#)
  - [Issues with Large Drives and OpenBSD](#)
- 

## Recent Updates

- [FAQ 4, Improved overview of the installation process](#)
  - [FAQ 12, Platform-Specific Questions](#)
  - [FAQ 1, What is included with OpenBSD?](#)
  - [FAQ 8, Should I use Ports or Packages?](#)
  - [FAQ 5, Common Problems when Compiling and Building](#)
  - [New PF FAQ!](#)
  - [FAQ 4, How can I get a dmesg\(8\) to report an install problem?](#)
- 

The FAQ maintainer is Nick Holland.

Additional contributors to the FAQ include Joel Knight, Eric Jackson, Wim Vandeputte

and Chris Cappuccio.

For information about and assisting in the translation of this FAQ and the rest of the OpenBSD website, see the [translation page](#).

Questions and comments regarding the FAQ may be directed to [faq@openbsd.org](mailto:faq@openbsd.org). General questions about OpenBSD should be directed to the appropriate [mail list](#).

## Back to OpenBSD



*OpenBSD FAQ Copyright © 1998-2003 OpenBSD*

\$OpenBSD: index.html,v 1.195 2003/10/26 16:45:11 nick Exp \$

"If you don't find it in the index, look very carefully through the entire catalogue."

**Sears, Roebuck, and Co., Consumer's Guide, 1897**



[\[FAQ Index\]](#) [\[To Section 2 - Other OpenBSD Information Resources\]](#)

# 1 - Introduction to OpenBSD

---

## Table of Contents

- [1.1 - What is OpenBSD?](#)
  - [1.2 - On what systems does OpenBSD run?](#)
  - [1.3 - Is OpenBSD really free?](#)
  - [1.4 - Why might I want to use OpenBSD?](#)
  - [1.5 - How can I help support OpenBSD?](#)
  - [1.6 - Who maintains OpenBSD?](#)
  - [1.7 - When is the next release of OpenBSD?](#)
  - [1.8 - What is included with OpenBSD?](#)
- 

## 1.1 - What is OpenBSD?

The [OpenBSD](#) project produces a freely available, multi-platform 4.4BSD-based UNIX-like operating system. Our [goals](#) place emphasis on correctness, [security](#), standardization, and [portability](#). OpenBSD supports binary emulation of most binaries from SVR4 (Solaris), FreeBSD, Linux, BSDI, SunOS, and HP-UX.

This FAQ specifically covers only the most recent release of OpenBSD, version 3.3.

## 1.2 - On what systems does OpenBSD run?

OpenBSD 3.3 runs on the following platforms:

- [i386](#) - CD bootable
- [sparc](#) - CD bootable
- [sparc64](#) - CD bootable
- [hp300](#) - FTP only
- [mac68k](#) - FTP only
- [macppc](#) - CD bootable
- [mvme68k](#) - FTP only
- [alpha](#) - FTP only
- [vax](#)
- [hppa](#) - FTP only \* *New for 3.3* \*

*bootable* means that OpenBSD will boot directly from the CD. The CD set will boot on several hardware platforms. See [chapter 3](#) of this FAQ for details of obtaining OpenBSD on CD.

Previous releases of OpenBSD also had a port for:

- [amiga](#) - removed after the 3.2 release
- [sun3](#) - removed after the 2.9 release
- [arc](#) - removed after the 2.3 release
- [mvme88k](#)
- [pmax](#) - removed after the 2.7 release

OpenBSD does not currently support more than one processor. See [FAQ 8, SMP](#) for more info.

## 1.3 - Is OpenBSD really free?

OpenBSD is all free. The binaries are free. The source is free. All parts of OpenBSD have reasonable copyright terms permitting free redistribution. This includes the ability to REUSE most parts of the OpenBSD source tree, either for personal or commercial purposes. OpenBSD includes NO further restrictions other than those implied by the original BSD license. Software which is written under stricter licenses cannot be included in the regular distribution of OpenBSD. This is intended to safeguard the free use of OpenBSD. For example, OpenBSD can be freely used for personal use, for academic use, by government institutions, by non-profit making organizations and by commercial organizations.

For further reading on other popular licenses read: <http://www.openbsd.org/policy.html>.

The maintainers of OpenBSD support the project largely from their own pockets. This includes the time spent programming for the project, equipment used to support the many ports, the network resources used to distribute OpenBSD to you, and the time spent answering questions and investigating users' bug reports. The OpenBSD developers are not independently wealthy and even small contributions of time, equipment, and resources make a big difference.

## 1.4 - Why might I want to use OpenBSD?

New users frequently want to know whether OpenBSD is superior to some other free UNIX-like operating system. That question is largely unanswerable and is the subject of countless (and useless) religious debates. Do not, under any circumstances, ask such a question on an OpenBSD mailing list.

Below are some reasons why we think OpenBSD is a useful operating system. Whether OpenBSD is right for you is a question that only you can answer.

- OpenBSD runs on many [different hardware platforms](#).
- OpenBSD is thought of by many security professionals to be the most [secure](#) UNIX-like operating system as the result of a 10-member 1.5-year long comprehensive source code security audit.
- OpenBSD is a full-featured UNIX-like operating system available in source form at no charge.
- OpenBSD integrates cutting-edge security technology suitable for building firewalls and [private network services](#) in a distributed environment.
- OpenBSD benefits from strong ongoing development in many areas, offering opportunities to work with emerging technologies with an international community of programmers and end-users.
- OpenBSD offers opportunities for ordinary people to participate in the development and testing of the product.

## 1.5 - How can I help support OpenBSD?

We are greatly indebted to the people and organizations that have contributed to the OpenBSD project. They are acknowledged by name on the [donations page](#).

OpenBSD has a constant need for several types of support from the user community. If you find OpenBSD useful, you are strongly encouraged to find a way to contribute. If none of the suggestions below are right for you, feel free to propose an alternative by sending e-mail to [donations@openbsd.org](mailto:donations@openbsd.org).

- [Buy an OpenBSD CD set](#). It includes the current full release of OpenBSD, and is bootable on many platforms. It also generates revenue to support the OpenBSD project, and reduces the strain on network resources used to deliver the distribution via the Internet. This inexpensive three-CD set includes full source. Remember, your friends need their own copy!
- [Donate money](#). The project has a constant need for cash to pay for equipment, network connectivity, and expenses relating to CD publishing. Manufacturing CDs requires an up-front out-of-pocket investment for the OpenBSD developers, without guaranteed return. Send e-mail to [donations@openbsd.org](mailto:donations@openbsd.org) to find out how to contribute. Even small donations make a profound difference.
- [Donate equipment and parts](#). The project has a constant need for general and specific hardware. Items such as IDE and SCSI disks, and various types of RAM are always welcome. For other types of hardware such as computer systems and motherboards, you should inquire as to current need. Write to [donations@openbsd.org](mailto:donations@openbsd.org) to arrange for shipment.
- Donate your time and skills. Programmers who enjoy writing operating systems are naturally always welcome, but there are literally dozens of other ways that people can be useful. Follow [mailing](#) lists and help answer new-user questions.
- Help maintain documentation by submitting new FAQ material (to [faq@openbsd.org](mailto:faq@openbsd.org)). Form a local [user group](#) and get your friends hooked on OpenBSD. Make a case to your employer for using OpenBSD at work. If you're a student, talk to your professors about using OpenBSD as a learning tool for Computer Science or Engineering courses. It's also worth mentioning one of the most important ways you should not try to "help" the OpenBSD project: do not waste your time engaging in operating system flame wars. It does not help the project to find new users and can cause substantial harm to important relationships that developers have with other developers.

## 1.6 - Who maintains OpenBSD?

OpenBSD is maintained by a development team spread across many different [countries](#). The project is coordinated by Theo de Raadt, located in Canada.

## 1.7 - When is the next release of OpenBSD?

The OpenBSD team makes a new release every six months, with target release dates of May 1 and November 1. More information on the development cycle can be found [here](#).

## 1.8 - What is included with OpenBSD?

OpenBSD is distributed with a number of third-party software products, including:

- [XFree86 4.2.1](#) the X Window environment. For i386, v3.3 X servers are also included for additional graphic chipset support. Installed with the `x*` .`tgz` [install file sets](#).
- [GCC 2.95](#) GNU C Compiler. The OpenBSD team has added the [Propolice](#) stack protection technology, enabled by default, and used throughout the OpenBSD userland and by default on applications compiled on OpenBSD. Installed as part of the `comp33` .`tgz` [file set](#).
- [Perl 5.8.0](#), with patches and improvements from the OpenBSD team.
- [Apache 1.3.27](#) web server. The OpenBSD team has added [default chrooting](#), privilege revocation, and other security-related improvements. Also includes `mod_ssl` 2.8 and DSO support.

- [OpenSSL 0.9.7beta3](#), with patches and improvements from the OpenBSD team.
- [Groff 1.15](#) text processor.
- [Sendmail 8.12.9](#) mail server.
- [BIND 9.2.2](#) DNS server. OpenBSD has implemented many improvements in chroot operation and other security-related issues.
- [Lynx 2.8.2rel.1](#) text web browser. With HTTPS support added, plus patches from the OpenBSD team.
- [Sudo v1.6.7](#), allowing users to run individual commands as root.
- [Ncurses 5.2](#).
- [KAME](#) IPv6.
- KTH Kerberos 1.1.1.
- Heimdal 0.4e with patches
- [OpenSSH 3.6](#)

As can be seen, the OpenBSD team often patches third-party products (typically) to improve the security or quality of the code. In some cases, the user will see no difference in operation, in other cases, there ARE operational differences which may impact some users. Keep these enhancements in mind before blindly adding different versions of the same software.

Of course, additional applications can be added through the OpenBSD [packages](#) and [ports](#) system.

[\[FAQ Index\]](#) [\[To Section 2 - Other OpenBSD Information Resources\]](#)



[www@openbsd.org](mailto:www@openbsd.org)

\$OpenBSD: faq1.html,v 1.51 2003/10/19 22:47:09 nick Exp \$



[\[FAQ Index\]](#) [\[To Section 1 - Introduction to OpenBSD\]](#) [\[To Section 3 - Obtaining OpenBSD\]](#)

## 2 - Other OpenBSD Information Resources

---

### Table of Contents

- [2.1 - Web Pages](#)
  - [2.2 - Mailing Lists](#)
  - [2.3 - Manual Pages](#)
  - [2.4 - Reporting Bugs](#)
- 

### 2.1 - Web Pages of Interest

The official website for the OpenBSD project is located at: <http://www.OpenBSD.org>.

A lot of valuable information can be found here regarding all aspects of the OpenBSD project.

Additional information for laptop users can be found at:  
<http://www.monkey.org/openbsd-mobile/>.

### 2.2 - Mailing Lists

The OpenBSD project maintains several popular mailing lists which users should subscribe to and follow. To subscribe to a mailing list, send an e-mail message to [majordomo@openbsd.org](mailto:majordomo@openbsd.org). That address is an automated subscription service. In the body of your message, on a single line, you should include a subscribe command for the list you wish to join. For example:

```
subscribe announce
```

The list processor will reply to you, asking for confirmation of your intent to join the list, so that others can not subscribe you to a flood of unwanted e-mail. The message will include instructions for several different ways to confirm, including a [list server](#) web page link, responding to the confirmation message or responding to [majordomo@openbsd.org](mailto:majordomo@openbsd.org). Use whatever method is convenient to you. You will note that all three techniques involve a unique and time limited identifying number, such as A56D-70D4-52C3, again to make sure *you* are really the person who requested this mail list subscription (this is *real* "opt-in").

Once you have confirmed your intent to join, you will be immediately added to the list, and the list processor will notify you that you were successfully added.

To unsubscribe from a list, you will again send an e-mail message to [majordomo@openbsd.org](mailto:majordomo@openbsd.org). It might look like this:

```
unsubscribe announce
```

If you have any difficulties with the mailing list system, please first read the help file which can be obtained by sending an e-mail message to [majordomo@openbsd.org](mailto:majordomo@openbsd.org) with a message body of "help".

Your subscription to the OpenBSD mail lists can also be maintained through the web interface at <http://lists.openbsd.org>

Some of the more popular OpenBSD mailing lists are:

- **announce** - Important announcements. This is a low-volume list.

- **security-announce** - Announcements of security issues. This is a low volume list.
- **misc** - General user questions and answers. This is the most active list, and should be the "default" for most questions.
- **bugs** - Bugs received via sendbug(1) and discussions about them.
- **source-changes** - Automated mailing of CVS source tree changes. Every time a developer commits a change to the OpenBSD source tree, [CVS](#) will send out a copy of the (usually brief) commit message via this list.
- **ports** - Discussion of the OpenBSD Ports Tree.
- **ports-changes** - Automated mailing of ports-specific CVS source tree changes.
- **advocacy** - Discussion on advocating OpenBSD, and topics that are just too off-topic for **misc**.

Before posting a question on **misc** or any other mailing list, please check the archives, for most common questions have been asked repeatedly. While it might be the first time you have encountered the problem or question, others on the mailing lists may have seen the same question several times in the last week, and may not appreciate seeing it again.

You can find several archives, other mailing list guidelines and more information on the [mailing lists page](#).

Another mailing list that may be of interest is [openbsd-mobile@monkey.org](mailto:openbsd-mobile@monkey.org). This mailing list is a discussion of the use of OpenBSD in mobile computing.

To subscribe to this list use:

```
'echo subscribe | mail "openbsd-mobile-request@monkey.org"'
```

The archives for that can be found at: <http://www.monkey.org/openbsd-mobile/archive/>.

## 2.3 - Manual Pages

OpenBSD comes with extensive documentation in the form of manual pages, as well as longer documents relating to specific applications. To access the manual pages and other documentation, be sure that you installed the man and misc sets.

Here is a list of some of the most useful manual pages for new users:

- [help\(1\)](#) - help for new users and administrators.
- [afterboot\(8\)](#) - things to check after the first complete boot.
- [boot\(8\)](#) - system bootstrapping procedures.
- [login.conf\(5\)](#) - format of the login class configuration file.
- [adduser\(8\)](#) - command for adding new users.
- [vipw\(8\)](#) - edit the master password file.
- [man\(1\)](#) - display the on-line manual pages.
- [sendbug\(1\)](#) - send a problem report (PR) about OpenBSD to a central support site.
- [disklabel\(8\)](#) - read and write disk pack label.
- [ifconfig\(8\)](#) - configure network interface parameters.
- [route\(8\)](#) - manually manipulate the routing tables.
- [netstat\(1\)](#) - show network status.
- [reboot, halt\(8\)](#) - stop and restart the system.
- [shutdown\(8\)](#) - close down the system at a given time.
- [boot\\_config\(8\)](#) - how to change kernel configuration at boot.

You can find all the OpenBSD man pages on the web at <http://www.openbsd.org/cgi-bin/man.cgi> as well as on your computer if you install the man33.tgz file set.

In general, if you know the name of a command or a manual page, you can read it by executing "man command". For example: "man vi" to read about the vi editor. If you don't know the name of the command, or if "man command" doesn't find the manual page, you can search the manual page database by executing "apropos something" or "man -k something" where "something" is a likely word that might appear in the title of the manual page you're looking for. For example:

```
# apropos "time zone"
tzfile (5) - time zone information
zdump (8) - time zone dumper
zic (8) - time zone compiler
```

The parenthetical numbers indicate the section of the manual in which that page can be found. In some cases, you may find manual pages with identical names living in separate sections of the manual. For example, assume that you want to know the format of the configuration files for the cron daemon. Once you know

the section of the manual for the page you want, you would execute "man n command" where n is the manual section number.

```
# man -k cron
cron (8) - clock daemon
crontab (1) - maintain crontab files for individual users
crontab (5) - tables for driving cron
# man 5 crontab
```

In addition to the UNIX manual pages, there is a typesettable document set (included in the `misc33.tgz` file set). It lives in the `/usr/share/doc` directory. You can format each document set with a "make" in the appropriate subdirectory. The `psd` subdirectory is the Programmer's Supplementary Documents distribution. The `smm` subdirectory is the System Manager's Manual. The `usd` subdirectory is the UNIX User's Supplementary Documents distribution. You can perform your "make" in the three distribution subdirectories, or you can select a specific section of a distribution and do a 'make' in its subdirectory. Some of the subdirectories are empty. By default, formatting the documents will result in PostScript output, suitable for printing. The PostScript output can be quite large -- you should assume 250-300% increase in volume. If you do not have access to a PostScript printer or display, you may also format the documents for reading on a terminal display. In each Makefile you'll need to add the flag "-Tascii" to each instance of the `groff(1)` commands (or execute it by hand). Some of the documents use the `ms` formatting macros, and some use the `me` macros. The Makefile in each document subdirectory (eg, `/usr/share/doc/usd/04.csh/Makefile`) will tell you which one to use. For example:

```
# cd /usr/share/doc/usd/04.csh
# groff -Tascii -ms tabs csh.1 csh.2 csh.3 csh.4 csh.a csh.g > csh.txt
# more csh.txt
```

The UNIX manual pages are generally more current and trustworthy than the typesettable documents. The typesettable documents sometimes explain complicated applications in more detail than the manual pages do.

For many, having a hardcopy of the man page can be useful. Here are the guidelines to making a printable copy of a man page.

## How do I display a man page source file? (i.e. one whose filename ends in a number, like `tcpdump.8`).

This is found throughout the src tree. The man pages are found in the tree unformatted, and many times through the use of `CVS`, they will be updated. To view these pages simply :

```
# nroff -mandoc <file> | more
```

## How do I get a plain man page with no formatting or control characters?

This is helpful to get the man page straight, with no non-printable characters.

Example:

```
# man <command> | col -b
```

## How can I get a PostScript copy of a man page that's print-ready?

Note that `[man_src_file]` must be the man page source file (probably a file that ends in a number; e.g., `tcpdump.8`). The PostScript versions of the man pages look very nice. They can be printed or viewed on-screen with a program like `gv` (GhostView). GhostView can be found in our [Ports Tree](#). Use the following `groff(1)` command options for getting a PostScript version from an OpenBSD system man page:

```
# groff -mandoc -Tps [man_src_file] > outfile.ps
```

## 2.4 - Reporting Bugs

Before submitting any bug report, please read <http://www.openbsd.org/report.html>.

Proper bug reporting is one of the most important responsibilities of end users. Very detailed information is required to diagnose most serious bugs. Developers frequently get bug reports via e-mail such as this:

```
From: joeuser@example.com
To: bugs@openbsd.org
Subject: HELP!!!
```

I have a PC and it won't boot!!!!!! It's a 486!!!!!!

Hopefully most people understand why such reports get summarily deleted. All bug reports should contain detailed information. If Joe User had really expected someone to help find this bug, he or she would have supplied more information... something like this:

```
From: smartuser@example.com
To: bugs@openbsd.org
Subject: 3.3-beta panics on a SparcStation2
```

OpenBSD 3.2 installed from an official CD-ROM installed and ran fine on this machine.

After doing a clean install of 3.3-beta from an FTP mirror, I find the system randomly panics after a period of use, and predictably and quickly when starting X.

This is the dmesg output:

```
OpenBSD 3.3-beta (GENERIC) #9: Mon Mar 17 12:37:18 MST 2003
  deraadt@sparc.openbsd.org:/usr/src/sys/arch/sparc/compile/GENERIC
real mem = 67002368
avail mem = 59125760
using 200 buffers containing 3346432 bytes of memory
bootpath: /sbus@1,f8000000/esp@0,800000/sd@1,0
mainbus0 (root): SUNW,Sun 4/75
cpu0 at mainbus0: CY7C601 @ 40 MHz, TMS390C602A FPU; cache chip bug
- trap page uncached
cpu0: 64K byte write-through, 32 bytes/line, hw flush cache enabled
memreg0 at mainbus0 iaddr 0xf4000000
clock0 at mainbus0 iaddr 0xf2000000: mk48t02 (eeprom)
timer0 at mainbus0 iaddr 0xf3000000 delay constant 17
auxreg0 at mainbus0 iaddr 0xf7400003
zs0 at mainbus0 iaddr 0xf1000000 pri 12, softpri 6
zstty0 at zs0 channel 0 (console i/o)
zstty1 at zs0 channel 1
zs1 at mainbus0 iaddr 0xf0000000 pri 12, softpri 6
zskbd0 at zs1 channel 0: reset timeout
zskbd0: no keyboard
zstty2 at zs1 channel 1: mouse
audioamd0 at mainbus0 iaddr 0xf7201000 pri 13, softpri 4
audio0 at audioamd0
sbus0 at mainbus0 iaddr 0xf8000000: clock = 20 MHz
dma0 at sbus0 slot 0 offset 0x400000: rev 1+
esp0 at sbus0 slot 0 offset 0x800000 pri 3: ESP100A, 25MHz, SCSI ID 7
scsibus0 at esp0: 8 targets
sd0 at scsibus0 targ 1 lun 0: <SEAGATE, ST1480 SUN0424, 8628> SCSI2 0/direct fixed
sd0: 411MB, 1476 cyl, 9 head, 63 sec, 512 bytes/sec, 843284 sec total
sd1 at scsibus0 targ 3 lun 0: <COMPAQPC, DCAS-32160, S65A> SCSI2 0/direct fixed
sd1: 2006MB, 8188 cyl, 3 head, 167 sec, 512 bytes/sec, 4110000 sec total
le0 at sbus0 slot 0 offset 0xc00000 pri 5: address 08:00:20:13:10:b9
le0: 16 receive buffers, 4 transmit buffers
cgsix0 at sbus0 slot 1 offset 0x0: SUNW,501-2325, 1152x900, rev 11
wsdisplay0 at cgsix0
wsdisplay0: screen 0 added (std, sun emulation)
fdc0 at mainbus0 iaddr 0xf7200000 pri 11, softpri 4: chip 82072
fd0 at fdc0 drive 0: 1.44MB 80 cyl, 2 head, 18 sec
root on sd0a
rootdev=0x700 rrootdev=0x1100 rawdev=0x1102
```

This is the panic I got when attempting to start X:

```
panic: pool_get(mclpl): free list modified: magic=78746572; page 0xfaa93000;
  item addr 0xfaa93000
Stopped at      Debugger+0x4:      jmpl      [%o7 + 0x8], %g0
RUN AT LEAST 'trace' AND 'ps' AND INCLUDE OUTPUT WHEN REPORTING THIS PANIC!
DO NOT EVEN BOTHER REPORTING THIS WITHOUT INCLUDING THAT INFORMATION!
```

```

ddb> trace
pool_get(0xfaa93000, 0x22, 0x0, 0x1000, 0x102, 0x0) at pool_get+0x2c0
sosend(0x16, 0xf828d800, 0x0, 0xf83b0900, 0x0, 0x0) at sosend+0x608
soo_write(0xfac0bf50, 0xfac0bf70, 0xfac9be28, 0xfab93190, 0xf8078f24, 0x0)
at soo_write+0x18
dofilewritew(0x0, 0xc, 0xfac0bf50, 0xf7fff198, 0x1, 0xfac0bf70) at
dofilewritew+0x12c
sys_writew(0xfac87508, 0xfac9bf28, 0xfac9bf20, 0xf80765c8, 0x1000, 0xfac0bf70)
at sys_writew+0x50
syscall(0x79, 0xfac9bfb0, 0x0, 0x154, 0xfcffffff, 0xf829dea0) at syscall+0x220
slowtrap(0xc, 0xf7fff198, 0x1, 0x154, 0x1, 0xfac87508) at slowtrap+0x1d8
ddb> ps
  PID  PPID  PGRP   UID  S      FLAGS  WAIT      COMMAND
 27765  8819  29550   0  3      0x86  netio     xconsole
  1668  29550  29550   0  3     0x4086  poll     fvwm
 15447  29550  29550   0  3     0x44186  poll     xterm
  8819  29550  29550  35  3     0x4186  poll     xconsole
  1238  29550  29550   0  3     0x4086  poll     xclock
 29550  25616  29550   0  3     0x4086  pause    sh
  1024  25523  25523   0  3     0x40184  netio    XFree86
*25523  25616  25523  35  2     0x44104          XFree86
 25616  30876  30876   0  3     0x4086  wait     xinit
 30876  16977  30876   0  3     0x4086  pause    sh
 16977   1  16977   0  3     0x4086  ttyin    csh
  5360   1   5360   0  3      0x84  select    cron
 14701   1  14701   0  3     0x40184  select    sendmail
 12617   1  12617   0  3      0x84  select    sshd
 27515   1  27515   0  3     0x184  select    inetd
  1904   1   1904   0  2      0x84          syslogd
  9125   1   9125   0  3      0x84  poll     dhclient
   7     0     0     0  3     0x100204  crypto_wa  crypto
   6     0     0     0  3     0x100204  aiodoned  aiodoned
   5     0     0     0  3     0x100204  syncer    update
   4     0     0     0  3     0x100204  cleaner  cleaner
   3     0     0     0  3     0x100204  reaper   reaper
   2     0     0     0  3     0x100204  pgdaemon  pagedaemon
   1     0     1     0  3      0x4084  wait     init
   0    -1     0     0  3     0x80204  scheduler  swapper

```

Thank you!

See [report.html](#) for more information on creating and submitting bug reports. Detailed information about your hardware is necessary if you think the bug *could be in any way* related to your hardware or hardware configuration. Usually, [dmesg\(8\)](#) output is sufficient in this respect. A detailed description of your problem is necessary. You will note that the [dmesg](#) described the hardware, the text explained why Smart User thought the system was not broken, (ran 3.2 properly), how this crash was caused (starting X), and the output of the debugger's "ps" and "trace" commands. In this case, Smart User provided output captured on a [serial console](#); if you can not do that, you will have to use paper and pencil to record the crash. (This was a real problem, and the information in the above report helped lead to a repair of this issue which impacted Sun4c systems.)

If Smart User had a working OpenBSD system from which he wanted to submit a bug report, he would have used the [sendbug\(1\)](#) utility to submit his bug report to the GNATS problem tracking system. Obviously you can't use [sendbug\(1\)](#) when your system won't boot, but you should use it whenever possible. You will still need to include detailed information about what happened, the exact configuration of your system, and how to reproduce the problem. The [sendbug\(1\)](#) command requires that your system be able to send electronic mail successfully on the Internet.

After submitting a bug report via [sendbug\(1\)](#), you will be notified by e-mail about the status of the report. You may be contacted by developers for additional information or with patches that need testing. You can also monitor the archives of the [bugs@openbsd.org](#) mailing list, details on the [mailing list page](#), or query the bug report database status at the on-line [Bug Tracking System](#).

[\[FAQ Index\]](#) [\[To Section 1 - Introduction to OpenBSD\]](#) [\[To Section 3 - Obtaining OpenBSD\]](#)



[www@openbsd.org](mailto:www@openbsd.org)

\$OpenBSD: faq2.html,v 1.65 2003/10/10 19:27:26 nick Exp \$



[\[FAQ Index\]](#) [\[To Section 2 - Other OpenBSD Information Resources\]](#) [\[To Section 4 - Installation Guide\]](#)

## 3 - Obtaining OpenBSD

---

### Table of Contents

- [3.1 - Buying an OpenBSD CD](#)
  - [3.2 - Buying OpenBSD T-Shirts](#)
  - [3.3 - Does OpenBSD provide an ISO image for download?](#)
  - [3.4 - Downloading via FTP or AFS](#)
  - [3.5 - Obtaining Current Source Code](#)
- 

### 3.1 - Buying an OpenBSD CD

Purchasing an OpenBSD CD is generally the best way to get started. Visit the ordering page to purchase your copy: <http://www.openbsd.org/orders.html>.

There are many good reasons to own an OpenBSD CD:

- CD sales support ongoing development of OpenBSD.
- Development of a multi-platform operating system requires constant investment in equipment.
- Your support in the form of a CD purchase has a real impact on future development.
- The CD contains binaries (and source) for all supported platforms.
- The CD is bootable on several platforms, and can be used to bootstrap a machine without a pre-existing installed operating system.
- The CD is useful for bootstrapping even if you choose to install a snapshot.
- Installing from CD is faster! Installing from CD preserves network connectivity resources.
- OpenBSD CDs always come with very nice stickers. Your system isn't fully complete without these. You can only get these stickers by buying a CD set or donating hardware.

If you're installing a release version of OpenBSD, you should use a CD.

### 3.2 - Buying OpenBSD T-Shirts

Yes, OpenBSD has t-shirts for your wearing enjoyment. You can view these at <http://www.OpenBSD.org/tshirts.html>. Enjoy :)

### 3.3 - Does OpenBSD provide an ISO image for download?

Some other open source operating systems are commonly distributed as CD-ROM ISO images. This is *not* how OpenBSD is distributed.

The OpenBSD project does not make the ISO images used to master the official CDs available for download. The reason is simply that we would like you to buy the CD sets, helping fund ongoing OpenBSD development. The official OpenBSD CD-ROM layout is copyright Theo de Raadt. Theo does not permit people to redistribute images of the official OpenBSD CDs. As an incentive for people to buy the CD set, some extras are included in the package as well (artwork, stickers etc).

Note that only the CD layout is copyrighted, OpenBSD itself is free. Nothing precludes someone else from downloading OpenBSD and making their own CD. If for some reason you want to download a CD image, try searching the mailing list archives for possible sources. Of course, any OpenBSD ISO images available on the Internet either violate Theo de Raadt's copyright or are not official images. The source of an unofficial image may or may not be trustworthy; it is up to you to determine this for yourself.

We suggest that people who want to download OpenBSD for free use the FTP install option. For those that need a bootable CD for their system, bootdisk ISO images (named `cd33.iso`) are available for a number of platforms which will then permit the rest of the system to be installed via FTP. These ISO images are only a few megabytes in size, and contain just the installation tools, not the actual file sets.

## 3.4 - Downloading via FTP or AFS

There are numerous international mirror sites offering FTP access to OpenBSD releases and snapshots. AFS access is also available. You should always use the site closest to you. Before you begin fetching a release or snapshot, you may wish to use [ping\(8\)](#) and [traceroute\(8\)](#) to determine which mirror site is nearest to you and whether that nearest mirror is performing adequately. Of course, your OpenBSD release CD is always closer than any mirror. Access information is here:

<http://www.openbsd.org/ftp.html>.

## 3.5 - Obtaining Current Source Code

Source to OpenBSD is freely redistributable and available at no charge. Generally the best way to get started with a current source tree is to install the source from the most recent CD and then configure AnonCVS to update it regularly. Information about AnonCVS, including how to set it up, is available here:

<http://www.openbsd.org/anoncv.html>.

or see [FAQ 8, CVS](#)

If you don't have sufficient network bandwidth to support AnonCVS, or if your Internet access is via UUCP, you can still keep your source current by using CTM instead of AnonCVS. If that's your situation, then starting with a recent release CD is even more important. Information about CTM, including how to set it up, is available here:

<http://www.openbsd.org/ctm.html>.

Yet another alternative is to get the source code from the web. You can do that through cvsweb at: <http://www.openbsd.org/cgi-bin/cvsweb/>.

[\[FAQ Index\]](#) [\[To Section 2 - Other OpenBSD Information Resources\]](#) [\[To Section 4 - Installation Guide\]](#)



[www@openbsd.org](mailto:www@openbsd.org)

\$OpenBSD: faq3.html,v 1.40 2003/07/23 01:53:01 nick Exp \$



[\[FAQ Index\]](#) [\[To Section 3 - Obtaining OpenBSD\]](#) [\[To Section 5 - Building the System from Source\]](#)

## 4 - OpenBSD 3.3 Installation Guide

---

### Table of Contents

- [4.1 - Overview of the OpenBSD installation procedure](#)
  - [4.2 - Pre-installation checklist](#)
  - [4.3 - Creating bootable OpenBSD install media](#)
    - [4.3.1 - Creating floppies on Unix](#)
    - [4.3.2 - Creating floppies on Windows or DOS](#)
    - [4.3.3 - Creating a boot CD](#)
  - [4.4 - Booting OpenBSD install media](#)
  - [4.5 - Performing an install](#)
    - [4.5.1 - Starting the install](#)
    - [4.5.2 - Setting up disks](#)
    - [4.5.3 - Setting the system hostname](#)
    - [4.5.4 - Configuring the network](#)
    - [4.5.5 - Choosing installation media](#)
    - [4.5.6 - Choosing filesets](#)
    - [4.5.7 - Small RAM procedure](#)
    - [4.5.8 - Finishing up](#)
    - [4.5.9 - Other Information Resources](#)
  - [4.6 - What files are needed for installation?](#)
  - [4.7 - How much space do I need for an OpenBSD installation?](#)
  - [4.8 - Multibooting OpenBSD/i386](#)
  - [4.9 - Sending your dmesg to dmesg@openbsd.org after the install](#)
  - [4.10 - Adding a file set after install](#)
  - [4.11 - What is 'bsd.rd'?](#)
  - [4.12 - Common installation problems](#)
    - [4.12.1 - Install hangs during MAKEDEV](#)
    - [4.12.2 - My Compaq only recognizes 16M RAM](#)
    - [4.12.3 - My i386 won't boot after install](#)
    - [4.12.4 - My machine booted, but hung at the ssh-keygen process](#)
    - [4.12.5 - I got the message "Failed to change directory" when doing an install](#)
  - [4.13 - Customizing the install process](#)
  - [4.14 - How can I install a number of similar systems?](#)
  - [4.15 - How can I get a dmesg\(8\) to report an install problem?](#)
- 

### 4.1 - Overview of the OpenBSD installation procedure

OpenBSD has a robust and adaptable text-based installation procedure, and can be installed from a single floppy disk. Most platforms follow a similar installation procedure; however there are some differences in the details. In all cases, you are urged to read the platform-specific INSTALL document in the *platform* directory on the CD-ROM or FTP sites (for example, `i386/INSTALL.i386`, `mac68k/INSTALL.mac68k` or `sparc/INSTALL.sparc`).

On most platforms, the OpenBSD installation uses a special kernel with a number of utilities and install scripts embedded in a preloaded RAM disk. After this kernel is booted, the operating system is extracted from a number of compressed [tar\(1\)](#) (`.tgz`) files. There are several ways to boot this install kernel:

- **Floppy disk:** Floppy disk images are provided which can be used to create an install floppy on another [Unix-like](#) system, or on a [DOS/Windows](#) system. Typical file names are `floppy33.fs`, though several platforms have multiple floppy images available.
- **CD-ROM:** On several platforms a CD-ROM image (`cd33.iso`) is provided allowing creation of a bootable CD-ROM. This just contains the

installation kernel - install files must still be retrieved via FTP or other source. You can, of course, build your own CD-ROM with whatever files and tools you desire.

- **bsd.rd**: The RAM disk kernel, intended for booting off either an already existing OpenBSD partition or booting over the network.
- **Network**: Some platforms support booting over a network.
- **Writing a file system image to disk**: a filesystem image that can be written to an existing partition, and then can be booted.
- **Bootable Tape**: Some platforms support booting from tape. These tapes can be made following the `INSTALL.platform` instructions.

Not every [platform](#) supports all boot options:

- **alpha**: Floppy, CD-ROM, writing a floppy image to hard disk.
- **hp300**: CD-ROM, network.
- **hppa**: Network.
- **i386**: Floppy, CD.
- **mac68k**: Installed (and booted) using MacOS utilities. See [INSTALL.mac68k](#) for details.
- **macppc**: CD-ROM, network.
- **mvme68k**: Network, bootable tape.
- **sparc**: Floppy, CD-ROM, network, writing image to existing swap partition, bootable tape.
- **sparc64**: Floppy (U1/U2 only), CD-ROM, network, writing image to existing partition.
- **vax**: Floppy, network.

All platforms other than mac68k can also use a [bsd.rd](#) to reinstall or upgrade.

Once the install kernel is booted, you have several options of where to get the [install file sets](#). Again, not every platform supports every option.

- **CD-ROM**: Of course, we prefer you use the [Official CD-ROM set](#), but for special needs, you can also make your own.
- **FTP**: Either one of the OpenBSD [FTP mirror sites](#) or your own local FTP server holding the file sets.
- **HTTP**: Either one of the OpenBSD [HTTP mirror sites](#) or your own local web server holding the file sets.
- **Local disk partition**: In many cases, you can install file sets from another partition on a local hard disk. For example, on [i386](#), you can install from a FAT partition or a CD-ROM formatted in either ISO9660 or Joliet format. In some cases, you will have to manually mount the file system before using it.
- **NFS**: Some platforms support using NFS mounts for the file sets.
- **Tape**: File sets can also be read from a supported tape.

## 4.2 - Pre-installation checklist

Before you start your install, you should have some idea what you want to end up with. You will want to know the following items, at least:

- Machine name
- Hardware installed and available
  - Verify compatibility with your platform's hardware compatibility page
  - If ISA, you also need to know hardware settings, and confirm they are as OpenBSD requires.
- Install method to be used (CD-ROM, FTP, etc.)
- Desired disk layout
  - Does existing data need to be saved elsewhere?
  - Will OpenBSD co-exist on this system with another OS? If so, how both will be booted? Will you need to install a "boot manager"?
  - Will the entire disk be used for OpenBSD, or do you want to keep an existing partition/OS (or space for a future one)?
  - How do you wish to sub-partition the OpenBSD part of your disk?
- Network settings, if not using DHCP:
  - Domain name
  - Domain Name Server(s) (DNS) address
  - IP addresses and subnet masks for each NIC
  - Gateway address
- Will you be running the X Window System?

## 4.3 - Creating bootable OpenBSD install media

As examples, we will look at the installation images available for the [i386](#) and [sparc](#) platforms.

The [i386](#) platform has five separate installation disk images to choose from:

- `f10ppy33.fs` (Desktop PC) supports many PCI and ISA NICs, IDE and simple SCSI adapters and some PCMCIA support. *Most* users will use this

image.

- **floppyB33.fs** (Servers) supports many RAID controllers, and some of the less common SCSI adapters. However, support for many standard SCSI adapters and many EISA and ISA NICs has been removed.
- **floppyC33.fs** (Laptops) supports the CardBus and PCMCIA devices found in many laptops.
- **cdrom33.fs** is, in effect a combination of all three boot disks. It can be used to make a bootable 2.88M floppy, or more commonly, as a boot image for a custom recordable CD.
- **cd33.iso** is an ISO9660 image that can be used to create a bootable CD with most popular CD-ROM creation software on most platforms. This is `cdrom33.fs` in a "ready-to-record" format.

Yes, there may be situations where one install disk is required to support your SCSI adapter and another disk is required to support your network adapter. Fortunately, this is a rare event, and can usually be worked around.

The [sparc](#) platform has three separate installation disk images to choose from:

- **floppy33.fs**: Supports systems with a floppy disk.
- **cd33.iso** An ISO image usable to make your own CD for booting SPARC systems with a CD-ROM.
- **miniroot33.fs** Can be written to a swap partition and booted.

### 4.3.1 - Creating floppies on Unix

To create a formatted floppy, use the [fdformat\(1\)](#) command to both format and check for bad sectors.

```
# fdformat /dev/rfd0c
Format 1440K floppy `/dev/rfd0c'? (y/n): y
Processing VVVVVVVVVVVVVVVVVVVVVVVVVVVVVVVVVVVVVVVVVVVVV done.
```

If your output is like the above example, then the disk is OK. However, if you do not see ALL "Vr"s then the disk is most likely bad, and you should try a new one.

Note that some Unix-like systems have different commands for formatting floppies. Refer to your system's documentation for the exact procedure.

Once you have a clean, formatted floppy it is time to write the installation image to floppy. For this, you can use the [dd\(1\)](#) utility. An example usage of `dd(1)` is below:

```
# dd if=floppy33.fs of=/dev/rfd0c bs=32k
```

Once the image is written, check to make sure that the copied image is the same as the original with the [cmp\(1\)](#) command. If the diskette is identical to the image, you will just see another prompt.

```
# cmp /dev/rfd0c floppy33.fs
```

### 4.3.2 - Creating floppies on Windows or DOS

This section describes how to write the installation images to floppy disk under Windows or DOS. You can get the tools mentioned below from the [tools](#) directory on any of the ftp mirrors, or from the `3.3/tools` directory on CD1 of the OpenBSD CD set.

To prepare a floppy in MS-DOS or Windows, first use the native formatting tools to format the disk.

To write the installation image to the prepared floppy you can use *rawrite*, *fdimage*, or *ntrw*. *rawrite* will not work on Windows NT, 2000 or XP.

Note that `FDIMAGE.EXE` and `RAWRITE.EXE` are both MS-DOS applications, and thus are limited to MS-DOS's "8.3" file naming convention. As `floppyB33.fs` and `floppyC33.fs` have longer file names, you will have to find out how your system stored the file in "8.3 format" before using `FDIMAGE.EXE` or `RAWRITE.EXE` to make your boot floppies.

Example usage of *rawrite*:

```
C:\> rawrite
RaWrite 1.2 - Write disk file to raw floppy diskette

Enter source file name: floppy33.fs
Enter destination drive: a
Please insert a formatted diskette into drive A: and press -ENTER- : Enter
```

Example usage of *fdimage*:

```
C:\> fdimage -q floppy33.fs a:
```

Example usage of *ntrw*:

```
C:\> ntrw floppy33.fs a:
3.5", 1.44MB, 512 bytes/sector
bufsize is 9216
1474560 bytes written
```

### 4.3.3 - Making a CD-ROM

You can create a CD-ROM using either the `cd33.iso` file or, in the case of the i386 platform, you can also use the `cdrom33.fs` as the bootable floppy image that is used to boot an i386 system from CD-ROM. The exact details here are left to the reader to determine with the tools they have at their disposal.

Some of the tools in OpenBSD are:

- [mkhybrid\(8\)](#)
- [cdrecord](#), part of the `cdrtools` collection in the [OpenBSD Ports System](#).

## 4.4 - Booting OpenBSD install media

### Booting i386

Booting an install image on the i386 PC platform is nothing new to most people. If you are using a floppy disk, simply insert the floppy into the floppy drive and boot the system. The install image will then load, provided floppy boot is enabled in your BIOS. If you want to boot from CD, you must go into your system's BIOS and set the boot options to allow booting from CD. Some older BIOSes do not have this option, and you must use a floppy for booting your installation image. Don't worry though; even if you boot from floppy you can still install from the CD.

### Booting sparc/sparc64

**NOTE:** On the [sparc64](#) platform, only the SBus machines (Ultra 1, Ultra 2) are bootable from floppy.

To boot from floppy, place the floppy disk with the OpenBSD installation image on it into the floppy drive. Then use the following command to boot from the floppy:

```
ok boot floppy
```

To boot from CD-ROM, place the OpenBSD CD-ROM disk into the drive. If your Sun only has one CD-ROM drive, then just go to the boot prompt, where you can `'boot cdrom'`:

```
ok boot cdrom
```

Of course, this will only work in new command mode. If you are at the old command mode prompt (a right arrow), type 'n' for the new command mode. (If you are using an old sparc that is pre-sun4c, you probably don't have a new command mode. In this case, you need to experiment.) If you have multiple CD-ROM devices, you need to boot from the correct one. Try `probe-scsi` from the new command mode.

```
ok probe-scsi

Target 0
  Unit 0   Disk      QUANTUM LIGHTNING 365S
Target 1
  Unit 0   Removable Disk  QUANTUM EMPIRE_1080S
Target 3
  Unit 0   Removable Disk  Joe's CD-ROM
```

Figure out which disk is the CD-ROM you want to boot from. Note the target number.

```
ok boot /sbus/esp/sd@X,0
```

## 4.5 - Performing an install

### 4.5.1 - Starting the install

Whatever your means of booting is, it is now time to use it. During the boot process, the kernel and all of the programs used to install OpenBSD are loaded into memory. The most common problem when booting is a bad floppy disk or a drive alignment problem. The boot floppy is quite tightly packed -- any bad spot will cause problems.

At almost any point during the OpenBSD install process, you can terminate the current install attempt by hitting CTRL-C and can restart it without rebooting by running `install` at the shell prompt.

When your boot is successful, you will see a lot of text messages scroll by. This text, on many architectures in white on blue, is the [dmesg](#), the kernel telling you what devices have been found, and where. Don't worry about remembering this text, as a copy is saved as `/var/run/dmesg.boot`. On some architectures, SHIFT+PGUP will let you examine text that has scrolled off the screen.

Then, you will see the following:

```
rootdev=0x1100 rrootdev=0x2f00 rawdev=0x2f02
erase ^?, werase ^W, kill ^U, intr ^C, status ^T
(I)nstall, (U)pgrade or (S)hell? i
```

And with that, we reach our first question. Most of the time, you have the three options shown:

- **Install:** load OpenBSD onto the system, overwriting whatever may have been there. Note that it is possible to leave some partitions untouched in this process, such as a `/home`, but otherwise, assume everything else is overwritten.
- **Upgrade:** Install a new set of [install files](#) on this machine, but do not overwrite any configuration information, user data, or additional programs. No disk formatting is done, nor are the `/etc` or `/var` directories overwritten. You will not be given the option of installing the `etc33.tgz` file. After the install, you will have to manually merge the changes of `etc33.tgz` into your system before you can expect it to be fully functional. This is an important step which must be done, as otherwise certain key services (such as [pf\(4\)](#)) may not start.  
**NOTE:** The Upgrade process is not designed to skip releases! While this will often work, it is not supported. For OpenBSD 3.3, upgrading 3.2 to 3.3 is the only supported upgrade. If you have to upgrade from an older version, a complete reinstall is recommended.
- **Shell:** Sometimes, you need to perform repairs or maintenance to a system which will not (or should not) boot to a normal kernel. This option will allow you to do maintenance to the system.

On occasion, you will not see the "Upgrade" option listed. After a *flag day* event, it is not possible to directly upgrade; one must rebuild the system from scratch. An example of this was the OpenBSD/sparc platform, which switched executable formats from `a.out` to ELF between 3.1 and 3.2, so a user upgrading to 3.2 or

3.3 on their SPARC must completely reload their system.

In this example, we will do an install, but the upgrade process is similar.

```
Welcome to the OpenBSD/i386 3.3 install program.
```

```
This program will help you install OpenBSD in a simple and rational way. At any prompt except password prompts you can run a shell command by typing '!foo', or escape to a shell by typing '!'. Default answers are shown in []'s and are selected by pressing RETURN. At any time you can exit this program by pressing Control-C and then RETURN, but quitting during an install can leave your system in an inconsistent state.
```

```
Specify terminal type: [vt220]
```

```
Do you wish to select a keyboard encoding table? [n] y
```

In most cases, the default terminal type is appropriate; however if you are using a [serial console](#) for install, don't just take the default, respond appropriately.

If you do not select a keyboard encoding table, a US keyboard layout will be assumed.

```
IS YOUR DATA BACKED UP? As with anything that modifies disk contents, this program can cause SIGNIFICANT data loss.
```

```
It is often helpful to have the installation notes handy. For complex disk configurations, relevant disk hardware manuals and a calculator are useful.
```

```
Proceed with install? [n] y
```

If you take the default here, the install process will terminate and drop you to a shell prompt.

## 4.5.2 - Setting up disks

Setting up disks in OpenBSD varies a bit between platforms. For [i386](#) and [macppc](#), disk setup is done in two stages. First, the OpenBSD slice of the hard disk is defined using `fdisk(8)`, then that slice is subdivided into OpenBSD partitions using `disklabel(8)`.

Some users may be a little confused by the terminology used here. It will appear we are using the word "partition" in two different ways. This observation is correct. There are two layers of partitioning in several OpenBSD platforms, the first, one could consider the Operating System partitioning, which is how multiple OSs on one computer mark out their own space on the disk, and the second one is how the OpenBSD partition is sub-partitioned into individual filesystems. The first layer is visible as a disk partition to DOS, Windows, and any other OS that can coexist with other Operating Systems on the IBM AT descended machines. The second layer of partitioning is visible only to OpenBSD and those OSs which can directly read an OpenBSD filesystem.

```
Cool! Let's get to it...
```

```
You will now initialize the disk(s) that OpenBSD will use. To enable all available security features you should configure the disk(s) to allow the creation of separate filesystems for /, /tmp, /var, /usr, and /home.
```

```
Available disks are: wd0.
```

```
Which one is the root disk? (or done) [wd0] Enter
```

The root disk is the disk the system will boot from, and normally where swap space resides. Usually, this will be the default -- if it isn't, you will need to know how to force your computer to boot from a non-standard disk. IDE disks will show up as `wd0`, `wd1`, etc., SCSI disks and RAID devices will show up as `sd0`, `sd1`, and so on. All the disks OpenBSD can find are listed here -- if you have drives which are not showing up, you have unsupported or improperly configured hardware.

```
Do you want to use *all* of wd0 for OpenBSD? [no] Enter
```

If you say "yes" to this question, the entire disk will be allocated to OpenBSD. This will result in a simple Master Boot Record and partition table being written out to disk -- one partition, the size of the entire hard disk, set to the OpenBSD partition type, and flagged as the bootable partition. This will be a common choice for most production uses of OpenBSD; however, there are some systems this should not be done on. Many Compaq systems, some Dell and other systems use a "maintenance" partition, which should be kept intact. If your system has any other partitions of any type you do not wish to erase, do not select "yes" to the above question.

For the sake of this example, we will assume the disk is to be split between OpenBSD and a pre-existing Windows 2000 partition, so we take the default of "no", which will take us into the [fdisk\(8\)](#) program. You can also get more information on [fdisk\(8\)](#) [here](#).

**Important Note:** Users with a large hard disk (larger than 8G on a newer i386, though on older machines and different platforms, often much smaller) will want to see [this section](#) before going any further.

```
You will now create a single MBR partition to contain your OpenBSD data. This
partition must have an id of 'A6'; must *NOT* overlap other partitions; and
must be marked as the only active partition.
```

```
The 'manual' command describes all the fdisk commands in detail.
```

```
Disk: wd0          geometry: 2586/240/63 [39100320 Sectors]
Offset: 0          Signature: 0xAA55

#  id  C  H  S  -  C  H  S  [  LBA Info:  start:  size  ]
-----
*0: 06  0  1  1  - 202 239 63 [ 63: 3069297 ] DOS > 32MB
1: 00  0  0  0  -  0  0  0 [  0: 0 ] unused
2: 00  0  0  0  -  0  0  0 [  0: 0 ] unused
3: 00  0  0  0  -  0  0  0 [  0: 0 ] unused
Enter 'help' for information
fdisk: 1> help
      help          Command help list
      manual        Show entire OpenBSD man page for fdisk
      reinit        Re-initialize loaded MBR (to defaults)
      setpid        Set the identifier of a given table entry
      disk          Edit current drive stats
      edit          Edit given table entry
      flag          Flag given table entry as bootable
      update        Update machine code in loaded MBR
      select        Select extended partition table entry MBR
      print         Print loaded MBR partition table
      write         Write loaded MBR to disk
      exit          Exit edit of current MBR, without saving changes
      quit          Quit edit of current MBR, saving current changes
      abort         Abort program without saving current changes
fdisk: 1>
```

A few commands are worthy of elaboration:

- **r** or **reinit**: Clears existing partition table, makes one big OpenBSD partition, flags it active. Equivalent to saying "yes" to the "use \*all\* of ..." question.
- **p** or **print**: Displays the current partition table in sectors. "p m" will show the partition table in megabytes, "p g" will show it in gigabytes.
- **e** or **edit**: edit or alter a table entry.
- **f** or **flag**: Marks a partition as the active partition, the one that will be booted from
- **exit** and **quit**: Careful on these, as some users are used to "exit" and "quit" having opposite meanings.

It is worth pointing out once again, a error here will result in significant data loss. If you are going to do this on a drive with important data, it might be worth practicing on a "disposable" drive, in addition to having a good backup.

Our drive here has a 1.5G partition for Windows 2000 (using the FAT filesystem). Looking at the info from the above display, we can see that the Windows partition occupies through cylinder 202 on the drive. So, we are going to allocate the rest of the disk to OpenBSD, starting at cylinder 203. You could also calculate OpenBSD's starting sector of 3069360 by adding the existing partition's starting sector (63) and its size (3069297).

You can edit the drive layout in either Cylinder/Heads/Sectors form or just raw sectors. Which is easier depends upon what you are doing; in this case, working around an existing partition, using CHS format will probably be easier.

```

fdisk: 1> e 1
      Starting      Ending      LBA Info:
#  id   C  H  S -   C  H  S [   start:      size   ]
-----
1: 00   0  0  0 -   0  0  0 [         0:         0 ] unused
Partition id ('0' to disable) [0 - FF]: [0] (? for help) a6
Do you wish to edit in CHS mode? [n] y
BIOS Starting cylinder [0 - 2585]: [0] 203
BIOS Starting head [0 - 239]: [0] Enter
BIOS Starting sector [1 - 63]: [0] 1
BIOS Ending cylinder [0 - 2585]: [0] 2585
BIOS Ending head [0 - 239]: [0] 239
BIOS Ending sector [1 - 63]: [0] 63
fdisk:*1> p
Disk: wd0      geometry: 2586/240/63 [39100320 Sectors]
Offset: 0      Signature: 0xAA55
      Starting      Ending      LBA Info:
#  id   C  H  S -   C  H  S [   start:      size   ]
-----
*0: 06   0  1  1 -  202 239 63 [         63:    3069297 ] DOS > 32MB
1: A6  203  0  1 - 2585 239 63 [    3069360:   36030960 ] OpenBSD
2: 00   0  0  0 -   0  0  0 [         0:         0 ] unused
3: 00   0  0  0 -   0  0  0 [         0:         0 ] unused
fdisk:*1> p m
Disk: wd0      geometry: 2586/240/63 [19092 Megabytes]
Offset: 0      Signature: 0xAA55
      Starting      Ending      LBA Info:
#  id   C  H  S -   C  H  S [   start:      size   ]
-----
*0: 06   0  1  1 -  202 239 63 [         63:    1499M] DOS > 32MB
1: A6  203  0  1 - 2585 239 63 [    3069360:   17593M] OpenBSD
2: 00   0  0  0 -   0  0  0 [         0:         0M] unused
3: 00   0  0  0 -   0  0  0 [         0:         0M] unused
fdisk:*1>

```

Note that the prompt changed to include an asterisk (\*) to indicate you have unsaved changes. As we can see from the output of `p m` we have not altered our Windows partition, we have successfully allocated the rest of the drive for OpenBSD, and the partitions do not overlap. We are in business. Almost.

What we haven't done is flagged the partition as active so the machine will boot OpenBSD on the next reboot:

```

fdisk:*1> f 1
Partition 1 marked active.
fdisk:*1> p
Disk: wd0      geometry: 2586/240/63 [39100320 Sectors]
Offset: 0      Signature: 0xAA55
      Starting      Ending      LBA Info:
#  id   C  H  S -   C  H  S [   start:      size   ]
-----
0: 06   0  1  1 -  202 239 63 [         63:    3069297 ] DOS > 32MB
*1: A6  203  0  1 - 2585 239 63 [    3069360:   36030960 ] OpenBSD
2: 00   0  0  0 -   0  0  0 [         0:         0 ] unused
3: 00   0  0  0 -   0  0  0 [         0:         0 ] unused
fdisk:*1>

```

And now, we are ready to save our changes:

```

fdisk:*1> w
Writing MBR at offset 0.
wd0: no disk label
fdisk: 1> q

```

## Creating a disklabel

The next step is to use [disklabel\(8\)](#) to slice up the OpenBSD partition. More details on using [disklabel\(8\)](#) can be found in [FAQ 14, disklabel](#).

Here is the partition information you chose:

```
Disk: wd0          geometry: 2586/240/63 [39100320 Sectors]
Offset: 0         Signature: 0xAA55
#  id  C  H  S -  C  H  S [  LBA Info:
#  id  C  H  S -  C  H  S [  start:  size  ]
-----
*0: 06  0  1  1 - 202 239 63 [ 63: 3069297 ] DOS > 32MB
1:  A6 203  0  1 - 2585 239 63 [ 3069360: 36030960 ] OpenBSD
2:  00  0  0  0 -  0  0  0 [ 0: 0 ] unused
3:  00  0  0  0 -  0  0  0 [ 0: 0 ] unused
```

You will now create an OpenBSD disklabel inside the OpenBSD MBR partition. The disklabel defines how OpenBSD splits up the MBR partition into OpenBSD partitions in which filesystems and swap space are created.

The offsets used in the disklabel are ABSOLUTE, i.e. relative to the start of the disk, NOT the start of the OpenBSD MBR partition.

```
disklabel: no disk label
```

```
WARNING: Disk wd0 has no label. You will be creating a new one.
```

```
# using MBR partition 1: type A6 off 3069360 (0x2ed5b0) size 36030960 (0x225c9f0)
```

```
Treating sectors 3069360-39100320 as the OpenBSD portion of the disk.
You can use the 'b' command to change this.
```

```
Initial label editor (enter '?' for help at any prompt)
```

```
> ?
```

```
Available commands:
```

```
  p [unit] - print label.
  M        - show entire OpenBSD man page for disklabel.
  e        - edit drive parameters.
  a [part] - add new partition.
  b        - set OpenBSD disk boundaries.
  c [part] - change partition size.
  d [part] - delete partition.
  D        - set label to default.
  g [d|b]  - Use [d]isk or [b]ios geometry.
  m [part] - modify existing partition.
  n [part] - set the mount point for a partition.
  r        - recalculate free space.
  u        - undo last change.
  s [path] - save label to file.
  w        - write label to disk.
  q        - quit and save changes.
  x        - exit without saving changes.
  X        - toggle expert mode.
  z        - zero out partition table.
  ? [cmdnd] - this message or command specific help.
```

```
Numeric parameters may use suffixes to indicate units:
```

```
'b' for bytes, 'c' for cylinders, 'k' for kilobytes, 'm' for megabytes,
```

```
'g' for gigabytes or no suffix for sectors (usually 512 bytes).
```

```
Non-sector units will be rounded to the nearest cylinder.
```

```
Entering '?' at most prompts will give you (simple) context sensitive help.
```

```
>
```

Again, a few of these commands could use a little elaboration:

- **p** - displays (prints) the current disklabel to the screen, and you can use the modifiers *k*, *m* or *g* for kilobytes, megabytes or gigabytes.
- **D** - Clears any existing disklabel, creates a new default disklabel which covers just the current OpenBSD partition. This can be useful if the disk previously had a disklabel on it, and the OpenBSD partition was recreated to a different size -- the old disk label may not get deleted, and may cause confusion.
- **m** - Modifies an existing entry in a disklabel. Do not over estimate what this will do for you. While it may alter the size of a disklabel partition, it will NOT alter the filesystem on the drive. Using this option and expecting it to resize existing partitions is a good way of losing large amounts of data.

Slicing up your disk properly is important. The answer to the question, "How should I partition my system?" is "Exactly how you need it". This will vary from

application to application. There is no universal answer. If you are unsure of how you want to partition your system, see [this discussion](#).

In this system, we have over 17G available for OpenBSD. That's a lot of space, and it isn't likely we will need most of it. So, we will deliberately not use absolute minimum sizes. We would rather have a few hundred megabytes of unused space than a kilobyte too little.

On the root disk, the two partitions 'a' and 'b' **must** be created. The installation process will not proceed until these two partitions are available. 'a' will be used for the root filesystem (/) and 'b' will be used as swap space.

After a little thought, we decide to create just enough partitions to allow the creation of the recommended separate filesystems (/ , /tmp , /var , /usr , /home) along with a swap partition:

- **wd0a:** / (root) - 150M. Should be more than enough.
- **wd0b:** (swap) - 300M.
- **wd0d:** /tmp - 120M. /tmp is used for building some software, 120M will probably be enough for most things.
- **wd0e:** /var - 80M. If this were to be a web or mail server, we'd have made this partition much larger, but, that's not what we are doing.
- **wd0g:** /usr - 2G. We want this partition to be large enough to load quite a few user applications, plus be able to update and rebuild the system if desired or needed. The [Ports tree](#) will be here as well, which will take almost 100M of this space before ports are built.
- **wd0h:** /home - 4G. This will allow plenty of user file space.

Now, if you add those up, you will see over 10G of space is unused! Unused space won't hurt anything, and it gives us flexibility to enlarge things in the future if need be. Need more /tmp? No problem, create a new one in the unused space, change */etc/fstab* and problem solved.

```
> p m
device: /dev/rwd0c
type: ESDI
disk: ESDI/IDE disk
label: ST320011A
bytes/sector: 512
sectors/track: 63
tracks/cylinder: 16
sectors/cylinder: 1008
cylinders: 16383
total sectors: 39102336
free sectors: 36030960
rpm: 3600

16 partitions:
#      size  offset  fstype  [fsize bsize  cpg]
  a: 17593.2M  1498.7M  unused      0    0
  c: 19092.9M    0.0M  unused      0    0
  i: 1498.7M    0.0M  MSDOS

> d a
> a a
offset: [3069360] Enter
size: [36030960] 150M
Rounding to nearest cylinder: 307440
FS type: [4.2BSD] Enter
mount point: [none] /
> a b
offset: [3376800] Enter
size: [35723520] 300M
Rounding to nearest cylinder: 614880
FS type: [swap] Enter
> a d
offset: [3991680] Enter
size: [35108640] 120m
Rounding to nearest cylinder: 245952
FS type: [4.2BSD] Enter
mount point: [none] /tmp
> a e
offset: [4237632] Enter
size: [34862688] 80m
Rounding to nearest cylinder: 164304
FS type: [4.2BSD] Enter
mount point: [none] /var
> a g
offset: [4401936] Enter
size: [34698384] 2g
Rounding to nearest cylinder: 4194288
```

```

FS type: [4.2BSD] Enter
mount point: [none] /usr
> a h
offset: [8596224] Enter
size: [30504096] 4g
Rounding to nearest cylinder: 8388576
FS type: [4.2BSD] Enter
mount point: [none] /home
> p m
device: /dev/rwd0c
type: ESDI
disk: ESDI/IDE disk
label: ST320011A
bytes/sector: 512
sectors/track: 63
tracks/cylinder: 16
sectors/cylinder: 1008
cylinders: 16383
total sectors: 39102336
free sectors: 22115520
rpm: 3600

16 partitions:
#      size  offset  fstype  [fsize bsize  cpg]
a:   150.1M 1498.7M 4.2BSD   1024  8192   16 # /
b:   300.2M 1648.8M      swap
c: 19092.9M   0.0M  unused         0    0
d:   120.1M 1949.1M 4.2BSD   1024  8192   16 # /tmp
e:    80.2M 2069.2M 4.2BSD   1024  8192   16 # /var
g:  2048.0M 2149.4M 4.2BSD   1024  8192   16 # /usr
h:  4096.0M 4197.4M 4.2BSD   1024  8192   16 # /home
i:   1498.7M   0.0M  MSDOS
> q
Write new label?: [y] Enter

```

You will note there is a *c* partition we seem to have ignored. This partition is your entire hard disk; don't attempt to alter it. You will also note the *i* partition wasn't defined by us; this is the pre-existing Windows 2000 partition. Partitions are not assigned any particular letters -- with the exception of *a* (root), *b* (swap) and *c* (entire disk), the rest of the partitions (through letter *p*) are available for use as you desire.

If you look closely at the output of the `disklabel`, you will note that your drive RPM rating is probably wrong. This is historical; the drive speed is not used in any way by the system. Do not worry about it.

## Configuring your mount points and formatting your filesystems

Now comes the final configuration of your mount points. If you configured the mount points through [disklabel\(8\)](#), this step consists of just verifying your selections; otherwise, you can specify them now.

```

The root filesystem will be mounted on wd0a.
wd0b will be used for swap space.
Mount point for wd0d (size=122976k), none or done? [/tmp] Enter
Mount point for wd0e (size=82152k), none or done? [/var] Enter
Mount point for wd0g (size=2097144k), none or done? [/usr] Enter
Mount point for wd0h (size=4194288k), none or done? [/home] Enter
Mount point for wd0d (size=122976k), none or done? [/tmp] done
Done - no available disks found.

```

You have configured the following partitions and mount points:

```

wd0a /
wd0d /tmp
wd0e /var
wd0g /usr
wd0h /home

```

```

The next step creates a filesystem on each partition, ERASING existing data.
Are you really sure that you're ready to proceed? [n] y
/dev/rwd0a:      307440 sectors in 305 cylinders of 16 tracks, 63 sectors
                150.1MB in 20 cyl groups (16 c/g, 7.88MB/g, 1920 i/g)

```

```

/dev/rwd0d:      245952 sectors in 244 cylinders of 16 tracks, 63 sectors
                120.1MB in 16 cyl groups (16 c/g, 7.88MB/g, 1920 i/g)
/dev/rwd0e:      164304 sectors in 163 cylinders of 16 tracks, 63 sectors
                80.2MB in 11 cyl groups (16 c/g, 7.88MB/g, 1920 i/g)
/dev/rwd0g:      4194288 sectors in 4161 cylinders of 16 tracks, 63 sectors
                2048.0MB in 261 cyl groups (16 c/g, 7.88MB/g, 1920 i/g)
/dev/rwd0h:      8388576 sectors in 8322 cylinders of 16 tracks, 63 sectors
                4096.0MB in 521 cyl groups (16 c/g, 7.88MB/g, 1920 i/g)
/dev/wd0a on /mnt type ffs (rw, asynchronous, local, ctime=Thu Oct 10 21:
50:36 2 002)
/dev/wd0h on /mnt/home type ffs (rw, asynchronous, local, nodev, nosuid,
ctime=Thu Oct 10 21:50:36 2002)
/dev/wd0d on /mnt/tmp type ffs (rw, asynchronous, local, nodev, nosuid,
ctime=Thu Oct 10 21:50:36 2002)
/dev/wd0g on /mnt/usr type ffs (rw, asynchronous, local, nodev, ctime=Th
u Oct 10 21:50:36 2002)
/dev/wd0e on /mnt/var type ffs (rw, asynchronous, local, nodev, nosuid,
ctime=Th u Oct 10 21:50:36 2002)

```

You may wonder why the installer again asks for mount points. This allows you to recover from any errors or omissions in the mount points specified during the creation of the disklabel. For instance, the installation process will automatically delete any duplicate mount points you enter during the configuration of the disklabel. The disklabel program will allow you to enter such duplicates, and thus they must be checked for after the disklabel program exits. The deleted duplicate mount points will result in partitions without mount points, that you must assign new mount points for if you wish to use the space.

Notice the "Are you really sure that you are ready to proceed?" question defaults to no, so you will have to deliberately tell it to proceed and format your partitions. If you chose no, you would simply be dropped into a shell and could start the install again by typing `install`, or just by rebooting again with your boot disk.

At this point all filesystems will be formatted for you. This could take some time depending on the size of the partitions and the speed of the disk.

### 4.5.3 - Setting the system hostname

Now you must set the system hostname. This value, along with the DNS domain name (specified [below](#)), will be saved in the file `/etc/myname`, which is used during normal boot to set the hostname of the system. If you do not set the domain name of the system, the default value of 'my.domain' will be used.

It is important to set this name now, because it will be used when the cryptographic keys for the system are generated during the first boot after installation. This generation takes place whether the network is configured or not.

```
Enter system hostname (short form, e.g. 'foo'): puffy
```

### 4.5.4 - Configuring the network

Now it is time to configure your network. The network must be configured if you are planning on doing a ftp or nfs based install, considering it will be based upon the information you are about to enter. Here is a walk through of the network configuration section of the install process.

```

Configure the network? [y] Enter
Available interfaces are: fxp0.
Which one do you wish to initialize? (or 'done') [fxp0] Enter
Symbolic (host) name for fxp0? [puffy] Enter
The default media for fxp0 is
    media: Ethernet autoselect (100baseTX full-duplex)
Do you want to change the default media? [n] Enter
IP address for fxp0? (or 'dhcp') 199.185.137.55
Netmask? [255.255.255.0] Enter
Done - no available interfaces found.
DNS domain name? (e.g. 'bar.com') [my.domain] example.com
DNS nameserver? (IP address or 'none') [none] 199.185.137.1
Use the nameserver now? [y] Enter
Default route? (IP address, 'dhcp' or 'none') 199.185.137.128
add net default: gateway 199.185.137.128
Edit hosts with ed? [n] Enter
Do you want to do any manual network configuration? [n] Enter

```

In the above example, we use a static IP address. As indicated, you can use "dhcp" instead on most platforms (not [Alpha](#)), assuming your environment supports it. In the case of DHCP, most of the information will be grabbed from the remote DHCP server; you will be given a chance to confirm it. Here is a sample of the network configuration part of the install, this time done with DHCP:

```
Configure the network? [y] Enter
Available interfaces are: fxp0.
Which one do you wish to initialize? (or 'done') [fxp0] Enter
Symbolic (host) name for fxp0? [puffy] Enter
The default media for fxp0 is
    media: Ethernet autoselect (100baseTX full-duplex)
Do you want to change the default media? [n] Enter
IP address for fxp0? (or 'dhcp') dhcp
Issuing hostname-associated DHCP request for fxp0.
Internet Software Consortium DHCP Client 2.0p15-OpenBSD
Listening on BPF/fxp0/00:08:c7:77:b4:6b
Sending on   BPF/fxp0/00:08:c7:77:b4:6b
Sending on   Socket/fallback/fallback-net
DHCPDISCOVER on fxp0 to 255.255.255.255 port 67 interval 1
DHCPOFFER from 199.185.137.128
DHCPREQUEST on fxp0 to 255.255.255.255 port 67
DHCPACK from 199.185.137.128
New Network Number: 199.185.137.0
New Broadcast Address: 199.185.137.255
bound to 199.185.137.55 -- renewal in 43200 seconds.
Done - no available interfaces found.
DNS domain name? (e.g. 'bar.com') [example.org] Enter
DNS nameserver? (IP address or 'none') [199.185.137.1] Enter
Use the nameserver now? [y] Enter
Default route? (IP address, 'dhcp' or 'none') [199.185.137.128] Enter
add net default: gateway 199.185.137.128
Edit hosts with ed? [n] Enter
Do you want to do any manual network configuration? [n] Enter
```

**NOTE:** Only **one** interface can easily be configured using DHCP during an install. If you attempt to configure more than one interface using DHCP you will encounter errors. You have to manually configure the additional interfaces after the installation.

Now, we set the password for the root account:

```
Password for root account? (will not echo) pAssWOrd
Password for root account? (again) pAssWOrd
```

Use a secure password for the root account. You will create other user accounts after the system is booted. From [passwd\(1\)](#):

```
The new password should be at least six characters long and not purely
alphabetic. Its total length must be less than _PASSWORD_LEN (currently
128 characters). A mixture of both lower and uppercase letters, numbers,
and meta-characters is encouraged.
```

## 4.5.5 - Choosing installation media

After your network is set up, the install script will give you a chance to make manual adjustments to the configuration. Then the filesystems you created will be mounted and a root password set. This will get your local disks ready for the OpenBSD packages to be installed upon them.

Next, you will get a chance to choose your installation media. The options are listed below.

```
You will now specify the location and names of the install sets you want to
load. You will be able to repeat this step until all of your sets have been
successfully loaded. If you are not sure what sets to install, refer to the
installation notes for details on the contents of each.
```

```
Sets can be located on a (m)ounted filesystem; a (c)drom, (d)isk or (t)ape
device; or a (f)tp, (n)fs or (h)ttp server.
```

```
Where are the install sets? c
Available CD-ROMs are: cd0.
```

In this example we are installing from CD-ROM. This will bring up a list of devices on your computer identified as a CD-ROM. Most people will only have one. If you need to, make sure you pick the device which you will use to install OpenBSD from.

**NOTE:** All possible sources for install sets are listed, but not all may be available on your system. e.g. (n)fs is shown but not all architectures allow NFS installations. If you choose a source that is not available, you will get an error message and be given the chance to choose another source for your installation sets.

```
Available CD-ROMs are: cd0.
Which one contains the install media? (or 'done') [cd0] Enter

Pathname to the sets? (or 'done') [3.3/i386] Enter
```

Here, you are prompted for which directory the installation files are, which is 3.3/i386/ on the official CD-ROM.

#### 4.5.6 - Choosing filesets.

Now it's time to choose which packages you will be installing. You can get a description of these files in [the next section](#). The files that the install program finds will be shown to you on the screen. Your job is just to specify which files you want. By default all the non-X packages are selected; however, some people may wish to limit this to the bare minimum required to run OpenBSD, which would be base33.tgz, etc33.tgz and bsd. Others will wish to install all packages. The example below is that of a full install.

```
The following sets are available. Enter a filename, 'all' to select
all the sets, or 'done'. You may de-select a set by prepending a '-'
to its name.
```

```
[X] bsd
[ ] bsd.rd
[X] base33.tgz
[X] etc33.tgz
[X] misc33.tgz
[X] comp33.tgz
[X] man33.tgz
[X] game33.tgz
[ ] xbase33.tgz
[ ] xshare33.tgz
[ ] xfont33.tgz
[ ] xserv33.tgz
```

```
File Name? (or 'done') [bsd.rd] all
```

```
The following sets are available. Enter a filename, 'all' to select
all the sets, or 'done'. You may de-select a set by prepending a '-'
to its name.
```

```
[X] bsd
[X] bsd.rd
[X] base33.tgz
[X] etc33.tgz
[X] misc33.tgz
[X] comp33.tgz
[X] man33.tgz
[X] game33.tgz
[X] xbase33.tgz
[X] xshare33.tgz
[X] xfont33.tgz
[X] xserv33.tgz
```

You can do all kinds of nifty things here -- `-x*` would remove all X components, if you changed your mind. In this case, we are going to load all the sets. While the system will run with fewer sets, either the starting default or installing all sets is recommended. More details on selecting sets [here](#).

Once you have successfully picked which packages you want, you will be prompted to make sure you want to extract these packages and they will then be installed. A progress bar will be shown that will keep you informed on how much time it will take. The times range greatly depending on what system it is you are installing OpenBSD on, the packages installed, and the speed of the source media. This part may from a few minutes to several hours.

```
File Name? (or 'done') [done] Enter
Ready to install sets? [y] Enter
Getting bsd ...
100% |*****| 4472 KB 00:03
Getting bsd.rd ...
100% |*****| 4190 KB 00:02
Getting base33.tgz ...
100% |*****| 30255 KB 00:21
Getting etc33.tgz ...
100% |*****| 1469 KB 00:01
Getting misc33.tgz ...
100% |*****| 1828 KB 00:01
Getting comp33.tgz ...
100% |*****| 16207 KB 00:13
Getting man33.tgz ...
100% |*****| 5921 KB 00:04
Getting game33.tgz ...
100% |*****| 2545 KB 00:01
Getting xbase33.tgz ...
100% |*****| 9073 KB 00:06
Getting xshare33.tgz ...
100% |*****| 1574 KB 00:02
Getting xfont33.tgz ...
100% |*****| 30666 KB 00:21
Getting xserv33.tgz ...
100% |*****| 14948 KB 00:11

Sets can be located on a (m)ounted filesystem; a (c)drom, (d)isk or (t)ape
device; or a (f)tp, (n)fs or (h)ttp server.
Where are the install sets? (or 'done')
```

At this point, you can pull additional files from other sources if desired, or hit 'done' if you have installed all the file sets you need.

If your system has a small amount of RAM (less than 20M on i386), do not answer that prompt quite yet!

#### 4.5.7 - Special steps for machines with little RAM

As OpenBSD has grown, the minimum RAM requirement has grown, and is likely to continue to increase. The next step in the install process will require more than 16M RAM, and will fail on older machines with less than 20M RAM (again, these are i386 numbers -- some other platforms will require far less RAM, though this trick can be used with them as well, if they are running near the lower-limits).

During the install process, there is normally no swap; the real RAM is all you have. The 'MAKEDEV' step that follows will require more than the rest of the install required. As a system with small amounts of RAM can still be very usable for many applications, working around this limitation is a quite useful trick.

The solution is to activate swap now. The swap partition has been created, the files are installed to the hard disk, the only trick here is to manually invoke it. So, do not just hit 'done' at the above prompt, but rather, hit '!', which will bring up a shell, and launch [swapon\(8\)](#) from the mounted hard drive:

```
Where are the install sets? (or 'done') !
Type 'exit' to return to install.
# /mnt/sbin/swapon /dev/wd0b
# exit
Where are the install sets? (or 'done') done
```

You can now resume the normal installation.

## 4.5.8 - Finishing up

You will now be asked if you plan to run X on this system. If you answer 'Y', `/etc/sysctl.conf` will be modified to include the line `machdep.allowaperture=1` or `machdep.allowaperture=2`, depending on your platform.

Your last task is to enter the time zone. Depending on where your machine lives, there are may be several equally valid answers for the question. In the example that follows, we used `US/Eastern`, but could also have used `EST5EDT` or `US/Michigan` and had the same result. Hitting `?` at the prompts will guide you through your choices.

```
Extract more sets? [n] Enter
Do you expect to run the X Window System? [y] Y
Saving configuration files.....done.
Generating initial host.random file .....done.
What timezone are you in? ('?' for list) [US/Pacific] ?
Africa/      Chile/      GB-Eire      Israel      NZ-CHAT      Turkey
America/     Cuba        GMT          Jamaica     Navajo       UCT
Antarctica/  EET        GMT+0       Japan       PRC          US/
Arctic/      EST        GMT-0       Kwajalein   PST8PDT      UTC
Asia/        EST5EDT    GMT0        Libya       Pacific/     Universal
Atlantic/    Egypt      Greenwich   MET         Poland       W-SU
Australia/   Eire       HST         MST         Portugal     WET
Brazil/      Etc/       Hongkong    MST7MDT     ROC         Zulu
CET          Europe/    Iceland     Mexico/     ROK         posix/
CST6CDT     Factory    Indian/     Mideast/    Singapore    posixrules
Canada/      GB         Iran        NZ          SystemV/     right/
What timezone are you in? ('?' for list) [US/Pacific] US
What sub-timezone of 'US' are you in? ('?' for list) ?
Alaska      Central    Hawaii       Mountain    Samoa
Aleutian    East-Indiana  Indiana-Starke  Pacific
Arizona     Eastern    Michigan     Pacific-New
Select a sub-timezone of 'US' ('?' for list): Eastern
Setting local timezone to 'US/Eastern'...done.
```

If you are concerned about very precise time, you may wish to read [this](#).

The last steps are for the system to create the `/dev` directory (which may take a while on some systems, especially if you had to use the [Small RAM](#) trick above), and install the boot blocks.

```
Making all device nodes...done.
Installing boot block...
boot: /mnt/boot
proto: /usr/mdec/biosboot
device: /dev/rwd0c
/usr/mdec/biosboot: entry point 0
proto bootblock size 512
room for 12 filesystem blocks at 0x16f
Will load 7 blocks of size 8192 each.
Using disk geometry of 63 sectors and 240 heads.
 0:  9 @(203 150 55) (3078864-3078872)
 1: 63 @(203 151 1) (3078873-3078935)
 2: 24 @(203 152 1) (3078936-3078959)
 3: 16 @(203 8 47) (3069910-3069925)
/mnt/boot: 4 entries total
using MBR partition 1: type 166 (0xa6) offset 3069360 (0x2ed5b0)
...done.

CONGRATULATIONS! Your OpenBSD install has been successfully completed!
To boot the new system, enter halt at the command prompt. Once the
system has halted, reset the machine and boot from the disk.
# halt
syncing disks... done

The operating system has halted.
Please press any key to reboot.
```

OpenBSD is now installed on your system and ready for its first boot, but before you do...

### Before you reboot

At this point, your system is installed and ready to be rebooted and configured for service. Before doing this, however, it would be wise to check out the [Errata page](#) to see if there are any bugs that would immediately impact you.

### After you reboot

One of your first things to read after you install your system is [afterboot\(8\)](#).

You may also find the following links useful:

- [Adding users in OpenBSD](#)
- [Initial Network Setup](#)
- [Man Pages of popular/useful commands](#)
- [OpenBSD man pages on the Web](#)
- [The OpenBSD Ports and Packages system for installing software](#), as well as [here](#) and [here](#)

### One last thing...

The OpenBSD developers ask you to [Send in a copy of your dmesg](#). This is really appreciated by the developers, and ultimately, all users.

## 4.5.9 - Other information resources

Additional documents already exist for those of you who might have special needs or interests. You can retrieve these from any of the [mirror ftp sites](#).

- [INSTALL.i386](#) - Comprehensive installation document. Similar documents exist for all platforms.
- [INSTALL.linux](#) - Installing OpenBSD along with Linux.
- [INSTALL.mbr](#) - Explaining the Master Boot Record.
- [INSTALL.pt](#) - Explaining Partition Tables.
- [INSTALL.dbr](#) - DOS Floppy Disk Boot Sector.
- [INSTALL.chs](#) - Explaining CHS Translation.
- [INSTALL.ata](#) - ATA/ATA-1/ATA-2/IDE/EIDE/etc FAQ
- [INSTALL.os2br](#) - The os2 Boot Sector.

## 4.6 - What files are needed for installation?

The complete OpenBSD installation is broken up into a number of separate *file sets*. Not every application requires every file set. Here is an overview of each:

- *bsd* - This is the Kernel. **Required**
- *bsd.rd* - [RAM disk kernel](#)
- *base33.tgz* - Contains the base OpenBSD system **Required**
- *etc33.tgz* - Contains all the files in /etc **Required**
- *comp33.tgz* - Contains the compiler and its tools, libs. **Recommended**
- *man33.tgz* - Contains man pages **Recommended**
- *misc33.tgz* - Contains misc info, setup documentation
- *game33.tgz* - Contains the games for OpenBSD
- *xbase33.tgz* - Contains the base install for X11
- *xfont33.tgz* - Contains X11's font server and fonts
- *xserv33.tgz* - Contains X11's X servers
- *xshare33.tgz* - Contains manpages, locale settings, includes, etc for X

## 4.7 - How much space do I need for an OpenBSD installation?

The following are minimum suggested filesystem sizes for a full system install. The numbers include enough extra space to permit you to run a typical home system that is connected to the Internet.

- These are minimum values.
- If you plan to install a significant amount of third party software, make your `/usr` partition large! **At least** triple these values!
- For a system that handles lots of email or web pages (stored, respectively, in `/var/mail` and `/var/www`) you will want to make your `/var` partition significantly larger, or put them on separate partitions.
- For a multiuser system which may generate lots of logs, you will still want to make your `/var` partition significantly larger (`/var/log`).
- If you plan to rebuild the kernel or system from source, you will want to make the `/usr` partition significantly larger, **at least** 800M-1G larger than indicated below.

As you read this, keep in mind that `/usr` and `/usr/X11R6` are usually both parts of the same filesystem, that is, `/usr`, as there is no big advantage to making them into separate filesystems.

SYSTEM	/	/usr	/var	/usr/X11R6
alpha	80M	250M	25M	140M
hp300	80M	250M	25M	140M
hppa	100M	200M	25M	120M
i386	60M	250M	25M	140M
mac68k	80M	250M	25M	100M
macppc	80M	250M	25M	140M
mvme68k	80M	250M	25M	100M
sparc	80M	250M	25M	120M
sparc64	80M	250M	25M	100M
vax	100M	200M	25M	120M

In addition, it is recommended that a `/tmp` partition be used. The `/tmp` partition is used in the compiling of ports, among other things, so how big you make it depends on what you do with it. 50M may be plenty for most people, but some large applications may require 100M or more of `/tmp` space.

When you are in the disklabel editor, you may choose to make your entire system have just an 'a' (main filesystem) and 'b' (swap) . The 'a' filesystem which you set up in disklabel will become your root partition, which should be the sum of all the 3 main values above (`/`, `/usr`, and `/var`) plus some space for `/tmp`. The 'b' partition you set up automatically becomes your system swap partition -- we recommend a minimum of 32MB but if you have disk to spare make it at least 64MB. If you have lots of disk space to spare, make this 256MB, or even 512MB.

Swap space is used to store system core dumps on in the event of a [crash\(8\)](#). If this is a consideration for you, your swap space should be slightly larger than the amount of main memory you are likely to ever have in the system. Note that upon reboot, [savecore\(8\)](#) will attempt to save the contents of the swap partition to a file in `/var/crash` so again, if this is a priority for you, your `/var` partition must have enough *free space* to hold these dump files.

There are five main reasons for using separate filesystems, instead of shoving everything into one or two filesystems:

- **Security:** You can mark some filesystems as 'nosuid', 'nodev', 'noexec', 'readonly', etc. This is now done by the install process, in fact, if you use the above described partitions.
- **Stability:** A user, or a misbehaved program, can fill a filesystem with garbage if they have write permissions for it. Your critical programs, which of course run on a different filesystem, do not get interrupted.
- **Speed:** A filesystem which gets written to frequently may get somewhat fragmented. (Luckily, the ffs filesystem, what OpenBSD uses, is not prone to heavy fragmentation.)
- **Integrity:** If one filesystem is corrupted for some reason then your other filesystems are still OK.
- **Size:** Many platforms have limits on the area of a disk where the boot ROM can load the kernel from. In some cases, this limit may be very small (504M for an older 486), in other cases, a much larger limit (8G on new i386 systems). As the kernel can end up anywhere in the root partition, the entire root partition should be within this area. For more details, see [this section](#). A good guideline might be to keep your `/` partition completely below 2G, unless you know your platform (and particular machine!) can handle more (or less!) than that.

Some additional thoughts on partitioning:

- For your first attempt at an experimentation system, one big `/` partition and swap may be easiest until you know how much space you need. By doing this you will be sacrificing some of the default security features of OpenBSD that require separate filesystems for `/`, `/tmp`, `/var`, `/usr` and `/home`.
- A system exposed to the Internet or other hostile forces should have a separate `/var` (and maybe even a separate `/var/log`) for logging.
- A `/home` partition can be nice. New version of the OS? Wipe and reload everything else, leave your `/home` partition untouched. Remember to save a copy of your configuration files, though!
- A separate partition for anything which may accumulate a large quantity of files that may need to be deleted can be faster to reformat and recreate than to delete. See the [upgrade-minifaq](#) for an example (`/usr/obj`).
- If you wish to rebuild your system from source for any reason, the source will be in `/usr/src`. If you don't make a separate partition for `/usr/src`, make sure `/usr` has sufficient space.
- A commonly forgotten fact: you do **not** have to allocate all space on a drive when you set the system up! Since you will now find it a challenge to buy a new drive smaller than 20G, it can make sense to leave a chunk of your drive unallocated. If you outgrow a partition, you can allocate a new partition from your unused space, [duplicate](#) your existing partition to the new partition, change `/etc/fstab` to point to the new partition, remount, you now have more space.

- If you make your partitions too close to the minimum size required, you will probably regret it later, when it is time to upgrade your system.
- If you permit users to write to `/var/www` (i.e., personal web pages), you might wish to put it on a separate partition, so you can use [quotas](#) to restrict the space they use, and if they fill the partition, no other parts of your system will be impacted.

## 4.8 - Multibooting OpenBSD/i386

Multibooting is having several operating systems on one computer, and some means of selecting the which OS is to boot. It is *not* a trivial task! If you don't understand what you are doing, you may end up deleting large amounts of data from your computer. New OpenBSD users are *highly* encouraged to start with a blank hard drive on a dedicated machine, and then practice your desired configuration on a non-production system before attempting a multiboot configuration on a production machine. [FAQ 14](#) has more information about the OpenBSD boot process.

When multibooting, the requirements of all operating systems must be met by your configuration. People often ask if there is a way around the [8G boot limit](#) of OpenBSD. While there are some programs that claim to get around various limits of various operating systems, none of them are known to do this with current versions of OpenBSD.

Here are several options to multibooting:

### Setting active partitions

This is probably the most overlooked, and yet, sometimes the best solution for multibooting. Simply set the active partition in whatever OS you are currently using to be the one you want to boot by default when you next boot. Virtually every OS offers a program to do this; OpenBSD's is [fdisk\(8\)](#), similar named programs are in Windows 9x and DOS, and many other operating systems. This can be highly desirable for OSs or systems which take a long time to shut down and reboot -- you can set it and start the reboot process, then walk away, grab a cup of coffee, and come back to the system booted the way you want it -- no waiting for the Magic Moment to select the next OS.

### Boot floppy

If you have a system that is used to boot OpenBSD infrequently (or don't wish other users of the computer to note anything has changed), consider using a boot floppy. Simply use one of the [standard OpenBSD install floppies](#), and create a `/etc/boot.conf` file (yes, you will also have to create an `/etc` directory on the floppy) with the contents:

```
boot hd0a:/bsd
```

to cause the system to boot from hard drive 0, OpenBSD partition 'a', kernel file `/bsd`. Note you can also boot from other drives with a line like: `"boot hd2a:/bsd"` to boot off the third hard drive on your system. To boot from OpenBSD, slip your floppy in, reboot. To boot from the other OS, eject the floppy, reboot.

In this case, the [boot\(8\)](#) program is loaded from the floppy, looks for and reads `/etc/boot.conf`. The `"boot hd0a:/bsd"` line instructs `boot(8)` where to load the kernel from -- in this case, the first HD the BIOS sees. Keep in mind, only a small file (`/boot`) is loaded from the floppy -- the system loads the entire kernel off the hard disk, so this only adds about five seconds to the boot process.

### Windows NT/2000/XP NTLDR

To multiboot OpenBSD and Windows NT/2000/XP, you can use NTLDR, the boot loader that NT uses. To multi-boot with NT, you need a copy of your OpenBSD Partition Boot Record (PBR). After running `installboot`, you can copy it to a file using [dd\(1\)](#):

```
# dd if=/dev/rsd0a of=openbsd.pbr bs=512 count=1
```

Now boot NT and put `openbsd.pbr` in C:. Add a line like this to the end of `C:\BOOT.INI`:

```
c:\openbsd.pbr="OpenBSD"
```

When you reboot, you should be able to select OpenBSD from the NT loader menu. There is much more information available about NTLDR at the [NTLDR Hacking Guide](#).

On Windows XP you can also edit the boot information using the GUI; see the [XP Boot.ini HOWTO](#).

Note: The Windows NT boot loader is only capable of booting OSs from the primary hard drive. You can not use it to load OpenBSD from the second drive on a system.

## Other boot loaders

Some other bootloaders OpenBSD users have used successfully include [GAG](#), [OSBS](#), [The Ranish Partition Manager](#) and [GRUB](#).

## OpenBSD and Linux (i386)

Please refer to [INSTALL.linux](#), which gives in depth instructions on getting OpenBSD working with Linux.

## 4.9 - Sending your dmesg to dmesg@openbsd.org after the install

Just to remind people, it's important for the OpenBSD developers to keep track of what hardware works, and what hardware doesn't work perfectly.

A quote from /usr/src/etc/root/root.mail

```
If you wish to ensure that OpenBSD runs better on your machines, please do us
a favor (after you have your mail system configured!) and type
    dmesg | mail dmesg@openbsd.org
so that we can see what kinds of configurations people are running. We will
use this information to improve device driver support in future releases.
(We would be much happier if this information was for the supplied GENERIC
kernel; not for a custom compiled kernel). The device driver information
we get from this helps us fix existing drivers.
```

Make sure you send email from an account that is able to also receive email so developers can contact you back if they have something they want you to test or change in order to get your setup working. It's not important at all to send the email from the same machine that is running OpenBSD, so if that machine is unable to receive email, just

```
$ dmesg | mail your-account@yourmail.dom
```

and then forward that message to

```
dmesg@openbsd.org
```

where your-account@yourmail.dom is your regular email account. (or transfer the dmesg output using ftp/scp/floppydisk/carrier-pigeon/...)

**NOTE** - Please send only GENERIC kernel dmesgs. Custom kernels that have device drivers removed are not helpful.

## 4.10 - Adding a file set after install

"Oh no! I forgot to add a file set when I did the install!"

Sometimes, you realize you really DID need comp33.tgz (or any other system component) after all, but you didn't realize this at the time you installed your system. Good news: There are two easy ways to add file sets after the initial install:

### Using the upgrade process

Simply boot your install media (CD-ROM or Floppy), and choose Upgrade (rather than Install). When you get to the lists of file sets to install, choose the sets you neglected to install first time around, select your source, and let it install them for you.

### Using tar(1)

The install file sets are simply compressed tar files, and you can expand them manually from the root of the filesystem:

```
# cd /
# tar xzvpf comp33.tgz
```

Do NOT forget the 'p' option in the above command in order to restore the file permissions properly!

One common mistake is to think you can use [pkg\\_add\(1\)](#) to add a missing file sets. This does not work. `pkg_add(1)` is for package files, not generic tar files like the install sets.

## 4.11 - What is 'bsd.rd'?

`bsd.rd` is a "RAM Disk" kernel. This file can be very useful; many developers are careful to keep it on the root of their system at all times.

Calling it a "RAM Disk kernel" describes the root filesystem of the kernel -- rather than being a physical drive, the utilities available after the boot of `bsd.rd` are stored in the kernel, and are run from a RAM-based filesystem. `bsd.rd` also includes a healthy set of utilities to allow you to do system maintenance and installation.

On some platforms, `bsd.rd` is actually the preferred installation technique -- you place this kernel on an existing filesystem, boot it, and run the install from it. On most platforms, if you have a running older version of OpenBSD, you can FTP a new version of `bsd.rd`, reboot from it, and install a new version of OpenBSD without using any removable media at all.

Here is an example of booting `bsd.rd` on an i386 system:

```
Using Drive: 0 Partition: 3
reading boot.....
probing pc0 com0 com1 apm mem[639k 255M a20=on]
disk fd0 hd0
>> OpenBSD/i386 BOOT 1.29
boot> boot hd0a:/bsd.rd
. . . normal boot to install . . .
```

As indicated, you will be brought to the install program, but you can also drop to the shell to do maintenance on your system.

The general rule on booting `bsd.rd` is to change your boot kernel from `/bsd` to `bsd.rd` through whatever means used on your platform.

## 4.12 - Common installation problems

### 4.12.1 - Install hangs during MAKEDEV

Usually, this is caused by a lack of physical RAM in the system. See [here](#).

### 4.12.2 - My Compaq only recognizes 16M RAM

*Some* Compaq systems have an issue where the full system RAM is not detected by the [OpenBSD second stage boot loader](#) properly, and only 16M may be detected and used by OpenBSD. This can be corrected either by creating/editing `/etc/boot.conf` file, or by entering commands at the "boot>" prompt before OpenBSD loads. If you had a machine with 64M RAM, but OpenBSD was only detecting the first 16M, the command you would use would be:

```
machine mem +0x3000000@0x1000000
```

to add 48M (0x3000000) after the first 16M (0x1000000). Typically, if you had a machine with this problem, you would enter the above command first at the install floppy/CD-ROM's boot> prompt, load the system, reboot, and create a `/etc/boot.conf` file with the above line in it so all future bootings will recognize all available RAM.

It has also been reported that a ROM update will fix this on *some* systems.

### 4.12.3 - My i386 won't boot after install

Your install seemed to go fine, but on first boot, you see no sign of OpenBSD attempting to boot. There are a few common reasons for this problem:

- **No partition was flagged active in fdisk(8).** To fix this, reboot the machine using the boot floppy or media, and "flag" a partition as "active" (bootable). See [here](#) and [here](#)
- **No valid boot loader was ever put on the disk.** If you answer "Y" to the "Use entire disk for OpenBSD?" question during the install, or use the "reinit" option of fdisk(8), the OpenBSD boot record is installed on the Master Boot Record of the disk; otherwise, the existing master boot code is untouched. This will be a problem if no other boot record existed. The solution is to boot the install media again, drop to the shell and invoke [fdisk\(8\)](#) and use the "update" option.
- **In some rare occasions, something may go wrong with the second stage boot loader install.** Reinstalling the second stage boot loader is discussed [here](#).
- **You mixed *a.out* and *ELF* boot disk and install files.** OpenBSD/i386 has transitioned from the older *a.out* format to the *ELF* format for binaries after 3.3-release. The [3.3-current snapshot's boot loader](#) can not boot an OpenBSD 3.3-release's kernel, nor can the 3.3-release boot loader boot a *-current* kernel. You must use a boot disk that matches the version of OpenBSD you intend to install. Failure to follow this will show itself with a message such as "failure(79)" and/or "Inappropriate file type or format".
- **You ignored all the [warnings](#) and [explanations](#) about the [8G boot limit](#).** This results in a hang at the very start of the boot process, sometimes with the message, "Bad magic".

### 4.12.4 - My (older, slower) machine booted, but hung at the ssh-keygen steps

It is very likely your machine is running fine, just taking a while to do the ssh key generation process. A SparcStation2 or a Macintosh Quadra may take 45 minutes or more to complete the three [ssh-keygen\(1\)](#) steps, some machines will take even longer. Just let it finish; it is only done once per install.

### 4.12.5 - I got the message "Failed to change directory" when doing an install

When doing an FTP install of a [snapshot](#) during the *-beta* stage of the [OpenBSD development cycle](#), you may see this:

```
Do you want to see a list of potential FTP servers? [y] ENTER
Getting the list from 192.128.5.191 (ftp.openbsd.org)... FAILED
Failed to change directory.
Server IP address or hostname?
```

This is normal and expected behavior during this pre-release part of the cycle. The install program looks for the FTP list on the primary FTP server in a directory that won't be available until the [release date](#), so you get the above message.

Simply use the [FTP mirror list](#) to find your favorite FTP mirror, and manually enter its name when prompted.

**Note: You should not see this if you are installing *-release* or from CD-ROM.**

## 4.13 - Customizing the install process

### siteXX.tgz file

The OpenBSD install/upgrade scripts allow the selection of a user-created set called "siteXX.tgz", where XX is the release version (e.g. 33). The siteXX.tgz file set is, like the other [file sets](#), a [gzip\(1\)](#) compressed [tar\(1\)](#) archive rooted in '/' and is un-tarred like the other sets with the options xzpf. This set will be installed last, after all other file sets.

This file set allows the user to add to and/or override the files installed in the 'normal' sets and thus customize the installation or upgrade.

Some example uses of a siteXX.tgz file:

- Create a siteXX.tgz file that contains all the file changes you made since first installing OpenBSD. Then, if you have to re-create the system you simply select siteXX.tgz during the re-install and all of your changes are replicated on the new system.
- Create a series of machine specific directories that each contain a siteXX.tgz file that contains files specific to those machine types. Installation of machines (e.g. boxes with different graphics cards) of a particular category can be completed by selecting the appropriate siteXX.tgz file.
- Put the files you routinely customize in a same or similar way in a siteXX.tgz file -- [/etc/skel](#) files, [/etc/pf.conf](#), [/var/www/conf/httpd.conf](#), [/etc/rc.conf](#), etc.

## install.site/upgrade.site scripts

As the last step in the install/upgrade process, the scripts look in the root directory of the newly installed/upgraded system for `install.site` or `upgrade.site`, as appropriate to the current process, and runs this script in an environment [chrooted](#) to the installed/upgraded system's root. Remember, the upgrade is done from a booted file system, so your target file system is actually mounted on `/mnt`. However, your script can be written as if it is running in the "normal" root of your file system. Since this script is run after all the files are installed, you have almost full functionality of your system (though, in single user mode) when your script runs.

Note that the `install.site` script would have to be in a `siteXX.tgz` file, while the `upgrade.site` script could be put in the root directory before the upgrade, or could be put in a `siteXX.tgz` file.

The scripts can be used to do anything possible in a script.

- Remove files that are installed/upgraded that you don't want present on the system.
- Remove/upgrade/install the [packages](#) you want on the installed system.
- Do an [immediate backup/archive](#) of the new system before you expose it to the rest of the world.

The combination of `siteXX.tgz` and `install.site/upgrade.site` files is intended to give the user broad customization capabilities without having to build their own custom install sets.

## 4.14 - How can I install a number of similar systems?

Here are some tools you can use when you have to deploy a number of similar OpenBSD systems.

### siteXX.tgz and install/upgrade.site files

See the [above](#) article.

### Restore from dump(8)

On most platforms, the boot media includes the [restore\(8\)](#) program, which can be used to restore a backup made by [dump\(8\)](#). Thus, you could boot from a [floppy](#), [CD](#), or [bsd.rd](#) file, then [fdisk](#), [disklabel](#), and [restore](#) the desired configuration from tape or other media, and install the [boot blocks](#). More details [here](#).

### Disk imaging

Unfortunately, there are no known disk imaging packages which are FFS-aware and can make an image containing only the active file space. Most of the major disk imaging solutions will treat an OpenBSD partition as a "generic" partition, and can make an image of the whole disk. This often accomplishes your goal, but usually with huge amounts of wasted space -- an empty, 10G `/home` partition will require 10G of space in the image, even if there isn't a single file in it. While you can typically install a drive image to a larger drive, you would not be able to directly use the extra space, and you would not be able to install an image to a smaller drive.

If this is an acceptable situation, you may find the [dd](#) command will do what you need, allowing you to copy one disk to another, sector-for-sector. This would provide the same functionality as commercial programs without the cost.

## 4.15 - How can I get a dmesg(8) to report an install problem?

When [reporting a problem](#), it is critical to include the complete system [dmesg\(8\)](#). However, often when you need to do this, it is because the system is working improperly or won't install so you may not have disk, network, or other resources you need to get the `dmesg` to the appropriate [mail list](#). There are other ways, however:

- **Floppy disk:** The boot disks and CD-ROM has enough tools to let you record your `dmesg` to an MSDOS floppy disk for reading on another machine. Place an MSDOS formatted floppy in your disk drive and execute the following commands:

```
mount -t msdos /dev/fd0a /mnt
dmesg > /mnt/dmesg.txt
umount /mnt
```

If you have another OpenBSD system, you can also write it to an OpenBSD compatible floppy -- often, the boot floppy has enough room on it to hold

the dmesg. In that case, leave off the "-t msdos" above.

- **Serial Console:** See [this article](#) on setting up the serial console, then capture the output to a file.
- **FTP:** Under some circumstances, you may be able to use the [ftp\(1\)](#) client on the boot disk or CD-ROM to send the dmesg to a local FTP server, where you can retrieve it later.

[\[FAQ Index\]](#) [\[To Section 3 - Obtaining OpenBSD\]](#) [\[To Section 5 - Building the System from Source\]](#)



[www@openbsd.org](mailto:www@openbsd.org)

\$OpenBSD: faq4.html,v 1.151 2003/10/14 02:26:21 nick Exp \$



the history of the source tree - it is never changed, and is what is on the [CDs](#) and [FTP servers](#). *-Current* is where active work is done, and turns into the next *-release* of OpenBSD.

The *-stable* (also known as the "Patch branch") is based on *-release*, and as one can see, it is a "branch" from the development path of OpenBSD. As important fixes are made to *-current*, they are "back ported" into the *-stable* branches. In the above illustration, the vertical dotted lines are bug fixes being incorporated into the *-stable* branches. You will also note that in the above example, the *3.0-stable* branch came to an end with *3.2-release*, and the *3.1-stable* branch came to an end with *3.3-release* -- old releases are typically supported up to two releases back. It takes resources and time to support older versions, while we might like to provide ongoing support for old releases, we would rather focus on new features. The *-stable* branch is, by design, very easy to build from *-release* of the same version (i.e., going from *3.3-release* to *3.3-stable*).

The *-stable* branch is *-release* plus patches found on the [errata page](#), and some simple fixes that do not merit an errata entry. Usually, the operation of *-stable* is the same as the *-release* it is based on. If the [man pages](#) have to change, it probably won't go into *-stable*. In other words, new device support will NOT be added to *-stable*, and new feature support will rarely be added unless it is considered very important.

Warning: *-current* is a moving target. It changes almost minute by minute, and may well change several times in the time it takes to retrieve the source code. As indicated earlier, there is no promise that the system compiles or that it works (of course, the hope is it does). It is entirely possible and not uncommon to get the *-current* source and have it fail to compile, whereas five minutes later, it may work just fine. **If you are not prepared to deal with this, stay away from *-current*.**

Most users should be running either *-stable* or *-release*. That being said, many people do run *-current* on production systems, and it is important that some people do so to identify bugs and test new features. However, if you don't know how to properly describe, diagnose and deal with a problem, don't tell yourself (or anyone else) that you are "helping the project" by running *-current*. "It didn't work!" is not a [useful bug report](#). "The recent changes to the pciide driver broke compatibility with my Slugchip-based IDE interface, dmesg of working and broken systems follow..." might be a useful report.

There are times where "normal" users may wish to live on the cutting edge and run *-current*. The most common reason is that the user has a device which is not supported by *-release* (and thus, not *-stable*), or wishes to use a new feature of the *-current*. In this case, the choice may be either *-current* or not using the device, and *-current* may be the lesser evil. However, one should not expect hand-holding from the developers.

## Snapshots

Between formal releases of OpenBSD, *snapshots* are made available through the [FTP sites](#). As the name implies, these are builds of whatever code is in the tree at the instant the builder grabbed a copy of the code for that particular platform. Remember, on some platforms, it may be DAYS before the snapshot build is completed and put out for distribution. There is no promise that the snapshots are completely functional, or even install. Often, a change that needs to be tested may trigger snapshot creation. Some platforms have snapshots built on an almost daily basis, others will be much less frequent. If you desire to run *-current*, a recent snapshot is often all you need, and upgrading to a snapshot is usually a good starting point before attempting to build *-current*.

It is sometimes asked if there is any way to get a copy of exactly the code used to build a snapshot. The answer is no. First, there is no significant benefit to this. Second, the snapshots are built as desired, as time permits, and as resources become available. On fast platforms, one might be able to build several snapshots in a day. On slower platforms, it may take a week or more to build a snapshot. Providing tags or markers in the source tree for each snapshot would be quite impractical.

## Keeping Things in Sync

It is important to understand that OpenBSD is an Operating System, intended to be taken as a whole, not a kernel with a bunch of utilities stuck on. You must make sure your kernel, "userland" (the supporting utilities and files) and [ports](#) tree are all in sync, or unpleasant things will happen. Said another way (because people just keep making the error), you can not run brand new [ports](#) on a month old system, or rebuild a kernel from *-current* source and expect it to work with a *-release* userland. Yes, this does mean you need to update your system if you want to run a new program which was added to the [ports](#) tree today. Sorry, but again,

OpenBSD has limited resources available.

One should also understand that when [upgrading by source](#), the update process is supported in **only one direction: from older to newer**, and from *-stable* to *-current*. You can not run *3.3-current* (or a snapshot), then decide you are living too dangerously, and step back to *3.3-stable*. You are on your own if you choose any path other than the supported option of reloading your system from scratch, do not expect assistance from the OpenBSD development team.

Yes, this does mean you should think long and hard before committing yourself to using *-current*.

## 5.2 - Why would I want to create my own custom kernel?

Several reasons, although this practice is generally geared towards knowledgeable users who have a good overall understanding of the system.

- Your computer has a very small amount of RAM and you want to preserve as much as possible by removing device drivers you don't use
- You wish to remove default options or add options which may not have been enabled by default
- You wish to enable experimental options

Under most circumstances you will NOT need to compile your own kernel. The GENERIC kernel will usually be all that you need. In fact, there are several reasons why you do not want to create your own kernel. The main reason is that it is very easy to make changes to the kernel configuration which look logical, but do not work. This is your danger sign. If something does not appear to work properly, please try the GENERIC kernel before sending in a bug report. Developers will usually ignore bug reports dealing with custom kernels, unless the problem can be reproduced in a GENERIC kernel as well. You have been warned.

## 5.3 - Kernel configuration files

OpenBSD kernel generation is controlled by configuration files, which are located in the `/usr/src/sys/arch/<arch>/conf/` directory by default. All architectures have a file, `GENERIC`, which is used to generate the standard OpenBSD kernel for that platform. There may also be other configuration files which are used to create kernels with different focuses, for example, for minimal RAM, diskless workstations, etc.

The configuration file is processed by [config\(8\)](#), which creates and populates a compilation directory in `../compile`, on a typical installation, that would be in `/usr/src/sys/arch/<arch>/compile/`. `config(8)` also creates a [Makefile](#), and other files required to successfully build the kernel.

Kernel Configuration Options are options that you add to your kernel configuration that place certain features into your kernel. This allows you to have exactly the support you want, without having support for unneeded devices. There are a multitude of options that allow you to customize your kernel. Here we will go over only some of them, those that are most commonly used. Check the [options\(4\)](#) man page for a complete list of options, and as these change from time to time, you should make sure you use a man page for the same version of OpenBSD you are building. You can also check the example configuration files that are available for your architecture.

**Do not add, remove, or change options in your kernel unless you actually have a reason to do so!** The only kernel configuration which is supported by the OpenBSD team is the GENERIC kernel, the combination of the options in `/usr/src/sys/arch/<arch>/conf/GENERIC` and `/usr/src/sys/conf/GENERIC` as shipped by the OpenBSD team (i.e., NOT edited). Reporting a problem on a customized kernel will almost always result in you being told to try to reproduce the problem with a GENERIC kernel. Not all options are compatible with each other, and many options are required for the system to work. There is no guarantee that just because you manage to get a custom kernel compiled that it will actually run.

You can see the platform-specific configuration files here:

- [alpha Kernel Configuration Files](#)
- [i386 Kernel Configuration files](#)
- [macppc Kernel Configuration files](#)
- [sparc Kernel Configuration Files](#)
- [sparc64 Kernel Configuration Files](#)
- [vax Kernel Configuration Files](#)
- [hppa Kernel Configuration Files](#)
- [Other Arch's](#)

Look closely at these files and you will notice a line near the top similar to:

```
include "../../../conf/GENERIC"
```

This means that it is referencing another configuration file, one that stores platform-independent options. When creating your Kernel Config, be sure to look through [sys/conf/GENERIC](#).

Kernel configuration options should be placed in your kernel configuration file in the format of:

```
option      name
```

For example, to place option "DEBUG" in the kernel, add a line like this:

```
option      DEBUG
```

Options in the OpenBSD kernel are translated into compiler preprocessor options, therefore an option like DEBUG would have the source compiled with option `-DDEBUG`, which is equivalent to doing a `#define DEBUG` throughout the kernel.

Sometimes, you may wish to disable an option that is already defined, typically in the `"src/sys/conf/GENERIC"` file. While you could modify a copy of that file, a better choice would be to use the `rmoption` statement. For example, if you really wanted to disable the in-kernel debugger (*not recommended!*), you would add a line such as:

```
rmoption DDB
```

in your kernel configuration file. `option DDB` is defined in `src/sys/conf/GENERIC`, but the above `rmoption` line deactivates it.

Once again, please see [options\(4\)](#) for more information about the specifics of these options. Also note that many of the options also have their own manual pages -- always read everything available about an option before adding or removing it from your kernel.

## 5.4 - Building your own kernel

Full instructions for creating your own custom kernel are in the [afterboot\(8\)](#) man page.

To compile your kernel from the CD-ROM you need to first have the source code available. The source is available on both the [official CD](#) (disk 3) and on the [FTP sites](#). The following example assumes that CD3 is mounted on `/mnt`:

```
# cd /usr/src
# tar xvzf /mnt/src.tar.gz
```

**Note:** If you are downloading from the FTP servers, you will find TWO files, *src.tar.gz* and *sys.tar.gz*. The first is the "userland" -- everything but the kernel, the second is the kernel source. Download and extract both of them as above, as for most uses, you will want both. On the CD-ROM, they are combined into one file.

Now to create your custom kernel it is easiest to start with the GENERIC kernel. This is located at `/usr/src/sys/arch/$ARCH/conf/GENERIC`, where `$ARCH` is your architecture. There are other sample configurations available in that directory as well. Here are two examples for compiling your kernel. The first example is compiling your kernel on a read-only source tree. The second on a writable source tree.

```
# cd /somewhere
# cp /usr/src/sys/arch/$ARCH/conf/SOMEFILE .
# vi SOMEFILE (to make the changes you want)
# config -s /usr/src/sys -b . SOMEFILE
```

followed by either:

```
# make depend
- OR -
# make clean
# make
```

You must run 'make depend' when you have made any changes (including updates and patches) to your source tree (in other words, almost always, unless you need to run 'make clean').

If you have made changes to your kernel configuration options, and/or made major changes to your source tree, you should use 'make clean' instead of the above 'make depend'. Note that it is always safe to do a 'make clean', though it may result in longer compile times, as more will be rebuilt.

To compile a kernel inside a writable source tree do the following:

```
# cd sys/arch/$ARCH/conf
# vi SOMEFILE (to make any changes you want)
# config SOMEFILE (read more about it here: config\(8\))
# cd ../compile/SOMEFILE
# make
```

Where `$ARCH` is the architecture you are using (e.g. `i386`). You can also do a **make depend** to make the dependencies for the next time you compile your kernel.

To move your kernel into place.

```
# cp /bsd /bsd.old
# cp /sys/arch/$ARCH/compile/SOMEFILE/bsd /bsd
```

To revert to your old kernel at boot you just need to

```
boot> bsd.old
```

and your old kernel will be loaded instead of `/bsd`.

Sometimes when you build a new kernel you will be required to install new bootblocks. To do so, read [FAQ 14, Installing Bootblocks](#), which will give you an overview on using OpenBSD's Bootloader.

## 5.5 - Boot-Time Configuration

Sometimes when booting your system you might notice that the kernel finds your device but maybe at the wrong IRQ. And maybe you need to use this device right away. Well, without rebuilding the kernel you can use OpenBSD's boot time kernel configuration. This will only correct your problem for one time. If you reboot, you will have to repeat this procedure. So, this is only meant as a temporary fix, and you should correct the problem by fixing and recompiling your kernel. Your kernel does however need **option BOOT\_CONFIG** in the kernel, which GENERIC does have.

Most of this document can be found in the man page [boot\\_config\(8\)](#).

To boot into the User Kernel Config, or UKC, use the `-c` option at boot time.

```
boot> boot wd0a:/bsd -c
```

Or whichever kernel it is you want to boot. Doing this will bring up a UKC prompt. From here you can issue commands directly to the kernel specifying devices you want to change or disable or even enable.

Here is a list of common commands in the UKC.

- `add device` - Add a device through copying another
- `change devno | device` - Modify one or more devices
- `disable devno | device` - Disable one or more devices
- `enable devno | device` - Enable one or more devices
- `find devno | device` - Find one or more devices
- `help` - Short summary of these commands
- `list` - List ALL known devices
- `exit/quit` - Continue Booting
- `show [attr [val]]` - Show devices with an attribute and optional with a specified value

Once you get your device configured, use `quit` or `exit` and continue booting. After doing so you should correct your Kernel configuration and Compile a new kernel. Refer to [Building your own kernel](#) for help.

## 5.6 - Getting more verbose output during boot

Getting more verbose output can be very helpful when trying to debug problems when booting. If you have a problem wherein your boot floppy won't boot and need to get more information, simply reboot. When you get to the "boot>" prompt, boot with `boot -c`. This will bring you into the UKC>, then do:

```
UKC> verbose
autoconf verbose enabled
UKC> quit
```

Now you will be given extremely verbose output upon boot.

## 5.7 - Using config(8) to change your kernel

The **-e** and **-u** options with [config\(8\)](#) can be extremely helpful and save wasted time compiling your kernel. The **-e** flag allows you to enter the UKC or User Kernel Config on a running system. These changes will then take place on your next reboot. The **-u** flag tests to see if any changes were made to the running kernel during boot, meaning you used **boot -c** to enter the UKC while booting your system.

The following example shows the disabling of the ep\* devices in the kernel. For safety's sake you must use the **-o** option which writes the changes out to the file specified. For example : **config -e -o bsd.new /bsd** will write the changes to bsd.new. The example doesn't use the **-o** option, therefore changes are just ignored, and not written back to the kernel binary. For more information pertaining to error and warning messages read the [config\(8\)](#) man page.

```
$ sudo config -e /bsd
OpenBSD 3.3 (GENERIC) #44: Sat Mar 29 13:22:05 MST 2003
  deraadt@i386.openbsd.org:/usr/src/sys/arch/i386/compile/GENERIC
warning: no output file specified
Enter 'help' for information
ukc> ?

      help                               Command help list
      add      dev                       Add a device
      base      8|10|16                  Base on large numbers
      change    devno|dev                Change device
      disable   attr val|devno|dev       Disable device
      enable    attr val|devno|dev       Enable device
      find      devno|dev                Find device
      list                               List configuration
      lines     count                     # of lines per page
      show      [attr [val]]             Show attribute
      exit                               Exit, without saving changes
      quit                               Quit, saving current changes
      timezone  [mins [dst]]             Show/change timezone
      nmbclust  [number]                 Show/change NMBCLUSTERS
      cachepct  [number]                 Show/change BUFCACHEPERCENT
      nkmpg     [number]                 Show/change NKMEMPAGES
      shmseg    [number]                 Show/change SHMSEG
      shmmaxpgs [number]                 Show/change SHMMAXPGS

ukc> list
  0 audio* at sb0|sb*|gus0|pas0|sp0|ess*|wss0|wss*|ym*|eap*|eso*|sv*|neo*|cmpci*
|clcs*|clct*|aulich*|autri*|auvia*|fms*|uaudio*|maestro*|esa*|yds*|emu* flags 0x0
  1 midi* at sb0|sb*|opl*|opl*|opl*|opl*|ym*|mpu*|autri* flags 0x0
  2 nsphy* at aue*|xe*|ef*|gx*|stge*|bge*|nge*|sk*|ste*|sis*|sf*|wb*|tx*|tl*|vr*
|ne0|ne1|ne2|ne*|ne*|ne*|dc*|dc*|rl*|fxp*|fxp*|xl*|xl*|ep0|ep0|ep0|ep*|ep*|ep*|e
p*|ep* phy -1 flags 0x0
  3 nsphyter* at aue*|xe*|ef*|gx*|stge*|bge*|nge*|sk*|ste*|sis*|sf*|wb*|tx*|tl*|
vr*|ne0|ne1|ne2|ne*|ne*|ne*|dc*|dc*|rl*|fxp*|fxp*|xl*|xl*|ep0|ep0|ep0|ep*|ep*|ep
*|ep*|ep* phy -1 flags 0x0
  4 qsphy* at aue*|xe*|ef*|gx*|stge*|bge*|nge*|sk*|ste*|sis*|sf*|wb*|tx*|tl*|vr*
|ne0|ne1|ne2|ne*|ne*|ne*|dc*|dc*|rl*|fxp*|fxp*|xl*|xl*|ep0|ep0|ep0|ep*|ep*|ep*|e
p*|ep* phy -1 flags 0x0
  5 inphy* at aue*|xe*|ef*|gx*|stge*|bge*|nge*|sk*|ste*|sis*|sf*|wb*|tx*|tl*|vr*
|ne0|ne1|ne2|ne*|ne*|ne*|dc*|dc*|rl*|fxp*|fxp*|xl*|xl*|ep0|ep0|ep0|ep*|ep*|ep*|e
p*|ep* phy -1 flags 0x0
  6 iophy* at aue*|xe*|ef*|gx*|stge*|bge*|nge*|sk*|ste*|sis*|sf*|wb*|tx*|tl*|vr*
|ne0|ne1|ne2|ne*|ne*|ne*|dc*|dc*|rl*|fxp*|fxp*|xl*|xl*|ep0|ep0|ep0|ep*|ep*|ep*|e
p*|ep* phy -1 flags 0x0
  7 eephy* at aue*|xe*|ef*|gx*|stge*|bge*|nge*|sk*|ste*|sis*|sf*|wb*|tx*|tl*|vr*
|ne0|ne1|ne2|ne*|ne*|ne*|dc*|dc*|rl*|fxp*|fxp*|xl*|xl*|ep0|ep0|ep0|ep*|ep*|ep*|e
p*|ep* phy -1 flags 0x0
  8 exphy* at aue*|xe*|ef*|gx*|stge*|bge*|nge*|sk*|ste*|sis*|sf*|wb*|tx*|tl*|vr*
|ne0|ne1|ne2|ne*|ne*|ne*|dc*|dc*|rl*|fxp*|fxp*|xl*|xl*|ep0|ep0|ep0|ep*|ep*|ep*|e
p*|ep* phy -1 flags 0x0
```

```
[...snip...]
ukc> disable ep
 67 ep0 disabled
 68 ep* disabled
 69 ep* disabled
155 ep0 disabled
156 ep0 disabled
157 ep* disabled
158 ep* disabled
210 ep* disabled
ukc> quit
not forced
```

In the above example, all ep\* devices are disabled in the kernel and will not be probed. In some situations where you have used the UKC during boot, via **boot -c**, you will need these changes to be written out permanently. To do this you need to use the **-u** option. In the following example, the computer was booted into the UKC and the wi(4) device was disabled. Since changes made with boot -c are NOT permanent, these changes must be written out. This example writes the changes made from boot -c into a new kernel binary `bsd.new`.

```
$ sudo config -e -u -o bsd.new /bsd
OpenBSD 3.3 (GENERIC) #44: Sat Mar 29 13:22:05 MST 2003
  deraadt@i386.openbsd.org: /usr/src/sys/arch/i386/compile/GENERIC
Processing history...
105 wi* disabled
106 wi* disabled
Enter 'help' for information
ukc> quit
```

## 5.8 - Common Problems when Compiling and Building

### 5.8.1 - The build stopped with a "Signal 11" error

Building OpenBSD and other programs from source is a task which pushes hardware harder than most others, making intensive use of CPU, disk and memory. As a result, if you have hardware which has a problem, the most likely time for that problem to appear is during a build. Signal 11 failures are *typically* caused by hardware problems, very often memory problems, but can also be CPU, main board, or heat issues. Your system may actually be very stable otherwise, but unable to compile programs.

You will probably find it best to repair or replace the components that are causing trouble, as problems may show themselves in other ways in the future. If you have hardware which you really wish to use and causes you no other problem, simply install a snapshot or a release.

For much more information, see the [Sig11 FAQ](#).

### 5.8.2 - "make build" fails with "cannot open output file snake: is a directory"

This is the result of two separate errors:

- **You did not fetch or update your CVS tree properly.** When doing a CVS checkout operation, you must use the **"-P"** option, when you update your source tree with CVS, you must use **"-Pd"** options to [cvs\(1\)](#), as documented in the [anoncvs guide](#), the [upgrade-minifaq](#) and the [FAQ](#). These options make sure new directories are added and removed from the tree as OpenBSD evolves.
- **You did not properly create the obj directory before your build.** Building the tree without a `/usr/obj` directory is not supported.

It is important to carefully follow the instructions when [getting and updating](#) your source code and [building](#) your tree.

[\[FAQ Index\]](#) [\[To Section 4 - Installation Guide\]](#) [\[To Section 6 - Networking\]](#)



[www@openbsd.org](mailto:www@openbsd.org)

\$OpenBSD: faq5.html,v 1.87 2003/10/10 00:37:54 nick Exp \$



[\[FAQ Index\]](#) [\[To Section 5 - Building the System from Source\]](#) [\[To Section 7 - Keyboard and Display Controls\]](#)

## 6 - Networking

---

### Table of Contents

- [6.0.1 - Before we go any further](#)
  - [6.1 - Initial network setup](#)
  - [6.2 - Packet Filter \(PF\)](#)
  - [6.4 - Dynamic Host Configuration Protocol](#)
  - [6.5 - Point to Point Protocol](#)
  - [6.6 - Tuning networking parameters](#)
  - [6.7 - Using NFS](#)
  - [6.9 - Setting up a PPTP connection in OpenBSD](#)
  - [6.10 - Setting up a bridge with OpenBSD](#)
- 

### 6.0.1 - Before we go any further

For the bulk of this document, it helps if you have read and at least partially understood the [Kernel Configuration and Setup](#) section of the FAQ, and the [ifconfig\(8\)](#) and [netstat\(1\)](#) man pages.

If you are a network administrator, and you are setting up routing protocols, if you are using your OpenBSD box as a router, if you need to go in depth into IP networking, you really need to read [Understanding IP Addressing](#). This is an excellent document. "Understanding IP Addressing" contains fundamental knowledge to build upon when working with IP networks, especially when you deal with or are responsible for more than one network.

If you are working with applications such as web servers, ftp servers, and mail servers, you may benefit greatly by [reading the RFCs](#). Most likely, you can't read all of them. Pick some topics that you are interested in, or that you use in your network environment. Look them up, find out how they are intended to work. The RFCs define many (thousands of) standards for protocols on the Internet and how they are supposed to work.

### 6.1 - Initial Network Setup

#### 6.1.1 - Identifying and Setting Up Your Network Interfaces

To start off, you must first identify your network interface. In OpenBSD, interfaces are named for the type of card, not for the type of connection. You can see your network card get initialized during the booting process, or after the booting process using the [dmesg\(8\)](#) command. You also have the chance of seeing your network interface using the [ifconfig\(8\)](#) command. For example, here is the output of dmesg for a Intel Fast Ethernet network card, which uses the device name fxp.

```
fxp0 at pci0 dev 10 function 0 "Intel 82557" rev 0x0c: irq 5, address 00:02:b3:2b:10:f7
inphy0 at fxp0 phy 1: i82555 10/100 media interface, rev. 4
```

If you don't know what your device name is, please look at the [supported hardware list](#) for your platform. You will find a list of many common card names and their OpenBSD device names here. Combine the short alphabetical device name (such as fxp) with a number assigned by the kernel and you have an interface name (such as fxp0).

You can find out what network interfaces have been identified by using the [ifconfig\(8\)](#) utility. The following command will show all network interfaces on a system. This sample output shows us only one physical ethernet interface, an [fxp\(4\)](#).

```
$ ifconfig -a
lo0: flags=8049<UP,LOOPBACK,RUNNING,MULTICAST> mtu 33224
    inet 127.0.0.1 netmask 0xff000000
    inet6 ::1 prefixlen 128
```

```

        inet6 fe80::1%lo0 prefixlen 64 scopeid 0x5
lo1: flags=8008<LOOPBACK,MULTICAST> mtu 33224
fxp0: flags=8843<UP,BROADCAST,RUNNING,SIMPLEX,MULTICAST> mtu 1500
    address: 00:04:ac:dd:39:6a
    media: Ethernet autoselect (100baseTX full-duplex)
    status: active
    inet 10.0.0.38 netmask 0xffffffff0 broadcast 10.0.0.255
    inet6 fe80::204:acff:fedd:396a%fxp0 prefixlen 64 scopeid 0x1
pflog0: flags=0<> mtu 33224
pfsync0: flags=0<> mtu 2020
sl0: flags=c010<POINTOPOINT,LINK2,MULTICAST> mtu 296
sl1: flags=c010<POINTOPOINT,LINK2,MULTICAST> mtu 296
ppp0: flags=8010<POINTOPOINT,MULTICAST> mtu 1500
ppp1: flags=8010<POINTOPOINT,MULTICAST> mtu 1500
tun0: flags=10<POINTOPOINT> mtu 3000
tun1: flags=10<POINTOPOINT> mtu 3000
enc0: flags=0<> mtu 1536
bridge0: flags=0<> mtu 1500
bridge1: flags=0<> mtu 1500
vlan0: flags=0<> mtu 1500
    address: 00:00:00:00:00:00
vlan1: flags=0<> mtu 1500
    address: 00:00:00:00:00:00
gre0: flags=9010<POINTOPOINT,LINK0,MULTICAST> mtu 1450
gif0: flags=8010<POINTOPOINT,MULTICAST> mtu 1280
gif1: flags=8010<POINTOPOINT,MULTICAST> mtu 1280
gif2: flags=8010<POINTOPOINT,MULTICAST> mtu 1280
gif3: flags=8010<POINTOPOINT,MULTICAST> mtu 1280

```

As you can see here, [ifconfig\(8\)](#) gives us a lot more information than we need at this point. But, it still allows us to see our interface. In the above example, the interface card is already configured. This is obvious because an IP network is already configured on `fxp0`, hence the values "inet 10.0.0.38 netmask 0xffffffff0 broadcast 10.0.0.255". Also, the **UP** and **RUNNING** flags are set.

Finally, you will notice several other interfaces come enabled by default. These are virtual interfaces that serve various functions. The following manual pages describe them:

- [lo](#) - Loopback Interface
- [pflog](#) - Packet Filter Logging Interface
- [sl](#) - SLIP Network Interface
- [ppp](#) - Point to Point Protocol
- [tun](#) - Tunnel Network Interface
- [enc](#) - Encapsulating Interface
- [bridge](#) - Ethernet Bridge Interface
- [vlan](#) - IEEE 802.1Q Encapsulation Interface
- [gre](#) - GRE/MobileIP Encapsulation Interface
- [gif](#) - Generic IPv4/IPv6 Tunnel Interface

If you don't have your interface configured, the first step is to create the `/etc/hostname.xxx` file, where the name of your interface will take the place of `xxx`. From the information in the examples above, the name would be `/etc/hostname.fxp0`. The layout of this file is simple:

```
address_family address netmask broadcast [other options]
```

(Much more detail about the format of this file can be found in the [hostname.if\(5\)](#) man page.)

A typical interface configuration file, configured for an IPv4 address, would look like this:

```
$ cat /etc/hostname.fxp0
inet 10.0.0.38 255.255.255.0 NONE
```

You could also specify media types for Ethernet, say, if you wanted to force 100baseTX full-duplex mode.

```
inet 10.0.0.38 255.255.255.0 NONE media 100baseTX mediaopt full-duplex
```

(Of course, you should never force full duplex mode unless both sides of the connection are set to do this! In the absence of special needs, media settings should be excluded.)

Or, you may want to use special flags specific to a certain interface. The format of the hostname file doesn't change much!

```
$ cat /etc/hostname.vlan0
inet 172.21.0.0 255.255.255.0 NONE vlan 2 vlandev fxp1
```

The next step from here is to setup your default gateway. To do this, simply put the IP of your gateway in the file `/etc/mygate`. This will allow for your gateway to be set upon boot. From here you should setup your nameservers, and your `/etc/hosts` file (see the [hosts\(5\)](#) man page). To setup your nameservers, you will create a file called `/etc/resolv.conf`. You can read more about the format of this file in the [resolv.conf\(5\)](#) man page. But for a standard usage, here is an example. In this example your domain servers are 125.2.3.4 and 125.2.3.5. You also belong in the domain "example.com".

```
$ cat /etc/resolv.conf
search example.com
nameserver 125.2.3.4
nameserver 125.2.3.5
lookup file bind
```

From here, you can either reboot or run the `/etc/netstart` script. You can do this by simply typing (as root):

```
# sh /etc/netstart
writing to routing socket: File exists
add net 127: gateway 127.0.0.1: File exists
writing to routing socket: File exists
add net 224.0.0.0: gateway 127.0.0.1: File exists
```

Notice that a few errors were produced. By running this script, you are reconfiguring things which are already configured. As such, some routes already exist in the kernel routing table. From here your system should be up and running. Again, you can check to make sure that your interface was setup correctly with [ifconfig\(8\)](#). You can also check your routes via [netstat\(1\)](#) or [route\(8\)](#). If you are having routing problems, you may want to use the `-n` flag to [route\(8\)](#) which prints the IP addresses rather than doing a DNS lookup and displaying the hostname. Here is an example of viewing your routing tables using both programs.

```
$ netstat -rn
Routing tables

Internet:
Destination          Gateway             Flags      Refs      Use      Mtu      Interface
default              10.0.0.1           UGS        0         86       -        fxp0
127/8                127.0.0.1         UGRS       0         0        -        lo0
127.0.0.1            127.0.0.1         UH         0         0        -        lo0
10.0.0/24            link#1             UC         0         0        -        fxp0
10.0.0.1             aa:0:4:0:81:d     UHL        1         0        -        fxp0
10.0.0.38            127.0.0.1         UGHS       0         0        -        lo0
224/4                127.0.0.1         URS        0         0        -        lo0

Encap:
Source               Port  Destination          Port  Proto SA(Address/SPI/Proto)

$ route show
Routing tables

Internet:
Destination          Gateway             Flags
default              10.0.0.1           UG
127.0.0.0            LOCALHOST          UG
localhost            LOCALHOST          UH
10.0.0.0             link#1             U
10.0.0.1             aa:0:4:0:81:d     UH
10.0.0.38            LOCALHOST          UGH
BASE-ADDRESS.MCA    LOCALHOST          U
```

## 6.1.2 - Setting up your OpenBSD box as a Gateway

This is the basic information you need to set up your OpenBSD box as a gateway (also called a router). If you are using OpenBSD as a router on the Internet, we suggest that you also read the Packet Filter setup instructions below to block potentially malicious traffic. Also, due to the low availability of [IPv4](#) addresses from network service providers and regional registries, you may want to look at Network Address Translation for information on conserving your IP address space.

The GENERIC kernel already has the ability to allow IP Forwarding, but needs to be turned on. You should do this using the [sysctl\(8\)](#) utility. To change this permanently you should edit the file [/etc/sysctl.conf](#) to allow for IP Forwarding. To do so add this line in that configuration file.

```
net.inet.ip.forwarding=1
```

To make this change without rebooting you would use the [sysctl\(8\)](#) utility directly. Remember though that this change will no longer exist after a reboot, and needs to be run as root.

```
# sysctl -w net.inet.ip.forwarding=1
net.inet.ip.forwarding: 0 -> 1
```

Now modify the routes on the other hosts on both sides. There are many possible uses of OpenBSD as a router, using software such as [routed\(8\)](#), [gated](#), [mrttd](#), and [zebra](#). OpenBSD has support in the ports collection for zebra, gated and mrttd. OpenBSD supports several T1, HSSI, ATM, FDDI, Ethernet, and serial (PPP/SLIP) interfaces.

### 6.1.3 - Setting up aliases on an interface

OpenBSD has a simple mechanism for setting up ip aliases on an interface. To do this simply edit the file `/etc/hostname.<if>`. This file is read upon boot by the [/etc/rc\(8\)](#) script, which is part of the [rc startup hierarchy](#). For the example, we assume that the user has an interface `dc0` and is on the network 192.168.0.0. Other important information:

- IP for dc0 is 192.168.0.2
- NETMASK is 255.255.255.0

A few side notes about aliases. In OpenBSD you use the interface name only. There is no difference between the first alias and the second alias. Unlike some other operating systems, OpenBSD doesn't refer to them as dc0:0, dc0:1. If you are referring to a specific aliased IP address with `ifconfig`, or adding an alias, be sure to say "`ifconfig int alias`" instead of just "`ifconfig int`" at the command line. You can delete aliases with "`ifconfig int delete`".

Assuming you are using multiple IP addresses which are in the same IP subnet with aliases, your netmask setting for each alias becomes 255.255.255.255. They do not need to follow the netmask of the first IP bound to the interface. In this example, `/etc/hostname.dc0`, two aliases are added to the device dc0, which, by the way, was configured as 192.168.0.2 netmask 255.255.255.0.

```
# cat /etc/hostname.dc0
inet 192.168.0.2 255.255.255.0 media 100baseTX
inet alias 192.168.0.3 255.255.255.255
inet alias 192.168.0.4 255.255.255.255
```

Once you've made this file, it just takes a reboot for it to take effect. You can, however, bring up the aliases by hand using the [ifconfig\(8\)](#) utility. To bring up the first alias you would use the command:

```
# ifconfig dc0 inet alias 192.168.0.3 netmask 255.255.255.255
```

To view these aliases you must use the command:

```
$ ifconfig -A
dc0: flags=8863<UP,BROADCAST,NOTRAILERS,RUNNING,SIMPLEX,MULTICAST>
    media: Ethernet manual
    inet 192.168.0.2 netmask 0xffffffff broadcast 192.168.0.255
    inet 192.168.0.3 netmask 0xffffffff broadcast 192.168.0.3
```

## 6.2 - Packet Filter (PF)

Packet Filter (from here on referred to as PF) is OpenBSD's system for filtering TCP/IP traffic and doing Network Address Translation. PF is also capable of normalizing and conditioning TCP/IP traffic and providing bandwidth control and packet prioritization. PF has been a part of the GENERIC OpenBSD kernel since OpenBSD 3.0. It is described in the new [PF User's Guide](#).

The old PF FAQ is still available [here](#).

## 6.4 - DHCP

### 6.4.1 DHCP Client

To use the DHCP client [dhclient\(8\)](#) included with OpenBSD, edit `/etc/hostname.xl0` (this is assuming your main ethernet interface is xl0. Yours might be ep0 or fxp0 or something else!) All you need to put in this hostname file is 'dhcp'

```
# echo dhcp >/etc/hostname.xl0
```

This will cause OpenBSD to automatically start the DHCP client on boot. OpenBSD will gather its IP address, default gateway, and DNS servers from the DHCP server.

If you want to start a dhcp client from the command line, make sure `/etc/dhclient.conf` exists, then try:

```
# dhclient fxp0
```

Where `fxp0` is the interface that you want to receive dhcp on.

No matter how you start the dhclient, you can edit the `/etc/dhclient.conf` file to **not** update your DNS according to the dhcp server's idea of DNS by first uncommenting the 'request' lines in it (they are examples of the default settings, but you need to uncomment them to override dhclient's defaults.)

```
request subnet-mask, broadcast-address, time-offset, routers,
       domain-name, domain-name-servers, host-name, lpr-servers, ntp-servers;
```

and then **remove** `domain-name-servers`. Of course, you may want to remove `hostname`, or other settings too.

## 6.4.2 DHCP Server

If you want to use OpenBSD as a DHCP server [dhcpd\(8\)](#), edit `/etc/rc.conf`. Set it up so that `dhcpd_flags="-q"` instead of `dhcpd_flags=NO`. Put the interfaces that you want dhcpd to **listen** on in `/etc/dhcpd.interfaces`.

```
# echo x11 x12 x13 >/etc/dhcpd.interfaces
```

Then, edit `/etc/dhcpd.conf`. The options are pretty self-explanatory.

```
option domain-name "example.com";
option domain-name-servers 192.168.1.3, 192.168.1.5;

subnet 192.168.1.0 netmask 255.255.255.0 {
    option routers 192.168.1.1;

    range 192.168.1.32 192.168.1.127;
}
```

This will tell your DHCP clients that the domain to append to DNS requests is `example.com` (so, if the user types in 'telnet joe' then it will send them to `joe.example.com`). It will point them to DNS servers `192.168.1.3` and `192.168.1.5`. For hosts that are on the same network as an ethernet interface on the OpenBSD machine, which is in the `192.168.1.0/24` range, it will assign them an IP address between `192.168.1.32` and `192.168.1.127`. It will set their default gateway as `192.168.1.1`.

If you want to start `dhcpd(8)` from the command line, after editing `/etc/dhcpd.conf`, try:

```
# dhcpd -q fxp0
```

Where `fxp0` is an interface that you want to start serving DHCP on. The `-q` flag makes `dhcpd(8)` quiet; otherwise it is very noisy.

If you are serving DHCP to a Windows box, you may want `dhcpd(8)` to give the client a 'WINS' server address. To make this happen, just the following line to your `/etc/dhcpd.conf`:

```
option netbios-name-servers 192.168.92.55;
```

(where `192.168.92.55` is the IP of your Windows or Samba server.) See [dhcp-options\(5\)](#) for more options that your DHCP clients may want.

## 6.5 - PPP

Point-to-Protocol is generally what is used to create a connection to your ISP via your modem. OpenBSD has 2 ways of doing this.

- [pppd\(8\)](#) - Which is the kernel ppp daemon.
- [ppp\(8\)](#) - Which is the userland ppp daemon.

The first one we will cover will be the userland PPP daemon. To start off you will need some simple information about your ISP. Here is a list of helpful information that you will need.

- Your ISP's dialup number
- Your nameserver
- Your username and password
- Your gateway

Some of these you can do without, but would be helpful in setting up your ppp. The userland PPP daemon uses the file [/etc/ppp/ppp.conf](#) as its configuration file. There are many helpful files in */etc/ppp* that can have different setups for many different situations. You should take a browse though that directory.

Also, make sure, that if you're not using a GENERIC kernel, that you have this line in your configuration file:

```
pseudo-device tun 2
```

## Initial Setup - for PPP(8)

Initial Setup for the userland PPP daemon consists of editing your */etc/ppp/ppp.conf* file. This file doesn't exist by default, but there is a file */etc/ppp/ppp.conf.sample* in which you can simply edit to create your own *ppp.conf* file. Here I will start with the simplest setup and probably most used setup. Here is a quick *ppp.conf* file that will simply connect to your ISP and set your default routes and nameserver. With this file all the information you need is your ISP's phone number and your username and password.

```
default:
set log Phase Chat LCP IPCP CCP tun command
set device /dev/cua01
set speed 115200
set dial "ABORT BUSY ABORT NO\\sCARRIER TIMEOUT 5 \" \" AT OK-AT-OK ATE1Q0 OK\\dATDT\\T TIMEOUT 40 CONNECT"
```

The section under the `default:` tag will get executed each time. Here we setup all our critical information. Here with "set log" we set our logging levels. This can be changed; refer to [ppp\(8\)](#) for more info on setting up logging levels. Our device gets set with "set device". This is the device that the modem is on. In this example the modem is on com port 2. Therefore com port 1 would be */dev/cua00*. With "set speed" we set the speed of our dialup connection and with "set dial" we set our dialup parameters. With this we can change our timeout time, etc. This line should stay pretty much as it is though.

Now we can move on and setup our information specific to our ISP. We do this by adding another tag under our **default:** section. This tag can be called anything you want, easiest to just use the name of your ISP. Here I will use **myisp:** as our tag referring to our ISP. Here is a simple setup incorporating all we need to get ourselves connected.

```
myisp:
set phone 1234567
set login "ABORT NO\\sCARRIER TIMEOUT 5 ogin:--ogin: ppp word: ppp"
set timeout 120
set ifaddr 10.0.0.1/0 10.0.0.2/0 255.255.255.0 0.0.0.0
add default HISADDR
enable dns
```

Here we have setup essential info for that specific ISP. The first option "set phone" sets your ISP's dialup number. The "set login" sets our login options. Here we have the timeout set to 5; this means that we will abort our login attempt after 5 seconds if no carrier. Otherwise it will wait for "login:" to be sent and send in your username and password. In this example our Username = ppp and Password = ppp. These values will need to be changed. The line "set timeout" sets the idle timeout for the entire connection duration to 120 seconds. The "set ifaddr" line is a little tricky. Here is a more extensive explanation.

```
set ifaddr 10.0.0.1/0 10.0.0.2/0 255.255.255.0 0.0.0.0
```

In the above line, we have it set in the format of "set ifaddr [myaddr/[nn] [hisaddr/[nn] [netmask [triggeraddr]]]". So the first IP specified is what we want as our IP. If you have a static IP address, you set it here. In our example we use /0 which says that no bits of this ip address need to match and the whole thing can be replaced. The second IP specified is what we expect as their IP. If you know this you can specify it. Again in our line we don't know what will be assigned, so we let them tell us. The third option is our netmask, here set to 255.255.255.0. If triggeraddr is specified, it is used in place of myaddr in the initial IPCP negotiation. However, only an address in the myaddr range will be accepted. This is useful when negotiating with some PPP implementations that will not assign an IP number unless their peer requests ``0.0.0.0".

The next option used "add default HISADDR" sets our default route to their IP. This is 'sticky', meaning that if their IP should change, our route will automatically be updated. With "enable dns" we are telling our ISP to authenticate our nameserver addresses. Do NOT do this if you are running a local DNS, as ppp will simply circumvent its use by entering some nameserver lines in */etc/resolv.conf*.

## Using PPP(8)

Now that we have our *ppp.conf* file setup we can start trying to make a connection to our ISP. I will detail some commonly used arguments with ppp.

- `ppp -auto myisp` - This will run ppp, configure your interfaces and connect to your ISP and then go into the background.
- `ppp -ddial myisp` - This is similar to -auto, but if your connection is dropped it will try and reconnect.

By using `/usr/sbin/ppp` with no options will put you into interactive mode. From here you can interact directly with the modem, it is great for debugging problems in your `ppp.conf` file.

## ppp(8) extras

In some situations you might want commands executed as your connection is made or dropped. There are two files you can create for just these situations. `/etc/ppp/ppp.linkup` and `/etc/ppp/ppp.linkdown`. Sample configurations can be viewed here:

- [ppp.linkup](#)
- [ppp.linkdown](#)

Extended information can be found at [FreeBSD Handbook entry on User PPP](#).

## 6.6 - Tuning networking parameters

### 6.6.1 - How can I tweak the kernel so that there are a higher number of retries and longer timeouts for TCP sessions?

You would normally use this to allow for routing or connection problems. Of course, for it to be most effective, both sides of the connection need to use similar values.

To tweak this, use `sysctl` and increase the values of:

```
net.inet.tcp.keepinittime
net.inet.tcp.keepidle
net.inet.tcp.keepintvl
```

Using `sysctl -a`, you can see the current values of these (and many other) parameters. To change one, use `sysctl -w`, as in `sysctl -w net.inet.tcp.keepidle=28800`.

### 6.6.2 - How can I turn on directed broadcasts?

Normally, you don't want to do this. This allows someone to send traffic to the broadcast address(es) of your connected network(s) if you are using your OpenBSD box as a router.

There are some instances, in closed networks, where this may be useful, particularly when using older implementations of the NetBIOS protocol. This is another `sysctl`. `sysctl -w net.inet.ip.directed-broadcast=1` turns this on. Read about [smurf attacks](#) if you want to know why it is off by default.

### 6.6.3 - I don't want the kernel to dynamically allocate a certain port

There is a `sysctl` for this also. From [sysctl\(8\)](#):

Set the list of reserved TCP ports that should not be allocated by the kernel dynamically. This can be used to keep daemons from stealing a specific port that another program needs to function. List elements may be separated by commas and/or whitespace.

```
# sysctl -w net.inet.tcp.baddynamic=749,750,751,760,761,871
```

It is also possible to add or remove ports from the current list.

```
# sysctl -w net.inet.tcp.baddynamic=+748
# sysctl -w net.inet.tcp.baddynamic=-871
```

## 6.7 - Simple NFS usage

NFS, or Network File System, is used to share a filesystem over the network. A few choice man pages to read before trying to setup a NFS server are:

- [nfsd\(8\)](#)

- [mountd\(8\)](#)
- [exports\(5\)](#)

This section will go through the steps for a simple setup of NFS. This example details a server on a LAN, with clients accessing NFS on the LAN. It does not talk about securing NFS. We presume you have already setup packet filtering or other firewalling protection, to prevent outside access. If you are allowing outside access to your NFS server, and you have any kind of sensitive data stored on it, we strongly recommend that you employ IPsec. Otherwise, people can potentially see your NFS traffic. Someone could also pretend to be the IP address which you are allowing into your NFS server. There are several attacks that can result. When properly configured, IPsec protects against these types of attacks.

Another important security note. Don't just add a filesystem to `/etc/exports` without some kind of list of allowed host(s). Without a list of hosts which can mount a particular directory, anyone on who can reach your host will be able to mount your NFS exports.

NFS depends upon [portmap\(8\)](#) to be running before it will operate. Portmap(8) is now off by default on OpenBSD 3.2 and later, so you must enable it in [rc.conf\(8\)](#) by changing the `portmap` line to read:

```
portmap=YES
```

and reboot to make it take effect.

The setup consists of a server with the ip **10.0.0.1**. This server will be serving NFS only to clients within that network. The first step to setting up NFS is to setup your `/etc/exports` file. This file lists which filesystems you wish to have accessible via NFS and defines who is able to access them. There are many options that you can use in your `/etc/exports` file, and it is best that you read the [exports\(5\)](#) man page. For this example we have an `/etc/exports` that looks like this:

```
#
# NFS exports Database
# See exports(5) for more information.  Be very careful, misconfiguration
# of this file can result in your filesystems being readable by the world.
/work -alldirs -ro -network 10.0.0 -mask 255.255.255.0
```

This means that the local filesystem `/work` will be made available via NFS. `-alldirs` specifies that clients will be able to mount at any point under the `/work` mount point. `-ro` specifies that it will only be allowed to be mounted read-only. The last two arguments specify that only clients within the 10.0.0.0 network using a netmask of 255.255.255.0 will be authorized to mount this filesystem. This is important for some servers that are accessible by different networks.

Once your `/etc/exports` file is setup, you can go ahead and setup your NFS server. You should first make sure that options `NFSSERVER` & `NFSCIENT` are in your kernel configuration. (GENERIC kernel has these options included.) Next, you should set `nfs_server=YES` in `/etc/rc.conf`. This will bring up both `nfsd(8)` and `mountd(8)` when you reboot. Now, you can go ahead and start the daemons yourself. These daemons need to be started as root, and you need to make sure that `portmap(8)` is running on your system. Here is an example of starting `nfsd(8)` which serves on both TCP and UDP using 4 daemons. You should set an appropriate number of NFS server daemons to handle the maximum number of concurrent client requests that you want to service.

```
# /sbin/nfsd -tun 4
```

Not only do you have to start the `nfsd(8)` server, but you need to start `mountd(8)`. This is the daemon that actually services the mount requests on NFS. To start `mountd(8)`, make sure an empty `mountdtab` file exists, and run the daemon:

```
# echo -n >/var/db/mountdtab
# /sbin/mountd
```

If you make changes to `/etc/exports` while NFS is already running, you need to make `mountd` aware of this! Just HUP it:

```
# kill -HUP `cat /var/run/mountd.pid`
```

## Checking Stats on NFS

From here, you can check to make sure that all these daemons are up and registered with RPC. To do this, use `rpcinfo(8)`.

```
$ rpcinfo -p 10.0.0.1
  program vers proto  port
  100000    2    tcp    111  portmapper
  100000    2    udp    111  portmapper
  100005    1    udp    633  mountd
  100005    3    udp    633  mountd
  100005    1    tcp    916  mountd
  100005    3    tcp    916  mountd
  100003    2    udp    2049 nfs
  100003    3    udp    2049 nfs
```

```

100003    2    tcp    2049    nfs
100003    3    tcp    2049    nfs

```

During normal usage, there are a few other utilities that allow you to see what is happening with NFS. One is [showmount\(8\)](#), which allows you to view what is currently mounted and who is mounting it. There is also [nfsstat\(8\)](#) which shows much more verbose statistics. To use [showmount\(8\)](#), try `/usr/bin/showmount -a host`. For example:

```

$ /usr/bin/showmount -a 10.0.0.1
All mount points on 10.0.0.1:
10.0.0.37:/work

```

## Mounting NFS Filesystems

NFS filesystems should be mounted via [mount\(8\)](#), or more specifically, [mount\\_nfs\(8\)](#). To mount a filesystem `/work` on host 10.0.0.1 to local filesystem `/mnt`, do this (note that you don't need to use an IP address; `mount` will resolve host names):

```
# mount -t nfs 10.0.0.1:/work /mnt
```

To have your system mount upon boot, add something like this to your `/etc/fstab`:

```
10.0.0.1:/work /mnt nfs rw 0 0
```

It is important that you use `0 0` at the end of this line so that your computer does not try to `fsck` the NFS filesystem on boot!!!! The other standard security options, such as `noexec`, `nodev`, and `nosuid`, should also be used where applicable. Such as:

```
10.0.0.1:/work /mnt nfs rw,nodev,nosuid 0 0
```

This way, no devices or `setuid` programs on the NFS server can subvert security measures on the NFS client. If you are not mounting programs which you expect to run on the NFS client, add `noexec` to this list.

## 6.9 - Setting up a PPTP connection in OpenBSD

**NOTE:** This does not apply to **ALL** ADSL providers, but much information can be gleaned from the setup here. This is known to work for [Inode](#), an ADSL provider in Austria.

To start off, you need to install `pptp`. The port is located at `/usr/ports/net/pptp`. Read [FAQ 8, Ports](#) for more information on the OpenBSD ports tree.

Because of a conflict between the In-Kernel [gre\(4\)](#) support and `pptp`, you will need to re-compile your kernel, removing support for `gre(4)`.

Patch to remove GRE(4) support.

```

Index: GENERIC
=====
RCS file: /cvs/src/sys/conf/GENERIC,v
retrieving revision 1.86
diff -u -r1.86 GENERIC
--- GENERIC      14 Mar 2002 00:42:25 -0000      1.86
+++ GENERIC      17 May 2002 01:52:17 -0000
@@ -87,7 +87,7 @@
 pseudo-device  enc      1      # option IPSEC needs the encapsulation interface
 pseudo-device  bridge  2      # network bridging support
 pseudo-device  vlan     2      # IEEE 802.1Q VLAN
-pseudo-device  gre      1      # GRE encapsulation interface
+#pseudo-device gre      1      # GRE encapsulation interface
 #pseudo-device strip   1      # Starmode Radio IP interface

 pseudo-device  pty      64     # pseudo-terminals

```

To recompile your kernel, check out OpenBSD source via `cvs` (refer to [AnonCVS](#) web page for more information), apply the following patch, and rebuild your kernel as per [FAQ 5, Building a kernel](#).

After you have the `pptp` package installed and a new kernel, you need to edit a few files to setup for your connection. This packages uses the in-house OpenBSD [ppp\(8\)](#), so if you are familiar with `ppp(8)`, much of the setup is the same. Also, refer to [FAQ 6, PPP](#).

- 1 - /etc/ppp/options
- 2 - /etc/ppp/pap-secrets

For the */etc/ppp/options* file, a setup like below will most likely do all that you need:

```
# cat /etc/ppp/options
name "LOGINNAME"
noauth
noipdefault
defaultroute
debug
```

LOGINNAME should be replaced with your User-ID.

The */etc/ppp/pap-secrets* a line like:

```
# cat /etc/ppp/pap-secrets
LOGINNAME 10.0.0.138 PASSWORD
```

Where LOGINNAME is your User-ID and PASSWORD is your password. 10.0.0.138 is the IP assigned to your MODEM in the case that you are using ADSL, etc. Make sure this file stays readonly by root (mode 600).

### 6.9.1 - Assigning an address to your Network Interface

In the above example, our modem came with a preconfigured interface of 10.0.0.138. We now need to assign an address to OUR interface. It's best to pick an IP close to the one given by your MODEM, or use the static IP assigned to you. Read more about setting up interfaces in [FAQ 6, Setup](#).

Once your interface is setup, you should be able to create a ppp connection with the command:

```
# /usr/local/sbin/ppp 10.0.0.138 &
```

Since this uses the in-house OpenBSD ppp(8), two processes are started. You can kill ppp by killing both these processes:

```
# kill -9 [pid of pppd]
$ kill -9 [pid of ppp]
```

It is recommended to open */var/log/messages* in a extra terminal window, to recognize possible problems.

```
# tail -f /var/log/messages
```

We also suggest that you put the startup command in */etc/rc.local* so that you automatically connect on reboot.

## 6.10 - Setting up a network bridge in OpenBSD

A [bridge](#) is a link between two or more separate networks. Unlike a router, packets transfer through the bridge "invisibly" -- logically, the two network segments appear to be one segment to nodes on either side of the bridge. The bridge will only forward packets that have to pass from one segment to the other, so among other things, they provide an easy way to reduce traffic in a complex network and yet allow any node to access any other node when needed.

Note that because of this "invisible" nature, an interface in a bridge may or may not have an IP address of its own. If it does, the interface has effectively two modes of operation, one as part of a bridge, the other as a normal, stand-alone NIC. If neither interface has an IP address, the bridge will pass network data, but will not be externally maintainable (which can be a feature).

### An example of a bridge application

One of my computer racks has a number of older systems, none of which have a built-in 10BASE-TX NIC. While they all have an AUI or AAUI connector, my supply of transceivers is limited to coax. One of the machines on this rack is an OpenBSD-based terminal server which always on and connected to the high-speed network. Adding a second NIC with a coax port will allow me to use this machine as a bridge to the coax network.

This system has two NICs in it now, an Intel EtherExpress/100 ([fxp0](#)) and a 3c590-Combo card ([ep0](#)) for the coax port. [fxp0](#) is the link to the rest of my network and will thus have an IP address, [ep0](#) is going to be for bridging only and will have no IP address. Machines attached to the coax segment will communicate as if they were

on the rest of my network. So, how do we make this happen?

The file `hostname.fxp0` contains the configuration info for the `fxp0` card. This machine is set up using DHCP, so its file looks like this:

```
$ cat /etc/hostname.fxp0
dhcp NONE NONE NONE NONE
```

No surprises here.

The `ep0` card is a bit different, as you might guess:

```
$ cat /etc/hostname.ep0
up media 10base2
```

Here, we are instructing the system to activate this interface using [ifconfig\(8\)](#) and set it to 10BASE-2 (coax). No IP address or similar information needs to be specified for this interface. The options the `ep` card accepts are detailed in its [man page](#).

Now, we need to set up the bridge. Bridges are initialized by the existence of a file named something like [bridgename.bridge0](#). Here is an example for my situation here:

```
$ cat /etc/bridgename.bridge0
add fxp0
add ep0
up
```

This is saying set up a bridge consisting of the two NICs, `fxp0` and `ep0`, and activate it. Does it matter which order the cards are listed? No, remember a bridge is very symmetrical -- packets flow in and out in both directions.

That's it! Reboot, and you now have a functioning bridge.

## Filtering on a bridge

While there are certainly uses for a simple bridge like this, it is likely you might want to DO something with the packets as they go through your bridge. As you might expect, [Packet Filter](#) can be used to restrict what traffic goes through your bridge.

Keep in mind, by the nature of a bridge, the same data flows through both interfaces, so you only need to filter on one interface. Your default "Pass all" statements would look something like this:

```
pass in on ep0 all
pass out on ep0 all
pass in on fxp0 all
pass out on fxp0 all
```

Now, let's say I wish to filter traffic hitting these old machines, I want only Web and SSH traffic to reach them. In this case, we are going to let all traffic in and out of the `ep0` interface, but filter on the `fxp0` interface, using `keep state` to handle the reply data:

```
# Pass all traffic through ep0
pass in quick on ep0 all
pass out quick on ep0 all

# Block fxp0 traffic
block in on fxp0 all
block out on fxp0 all

pass in quick on fxp0 proto tcp from any to any port {22, 80} \
    flags S/SA keep state
```

Note that this rule set will prevent anything but incoming HTTP and SSH traffic from reaching either the bridge machine or any of the other nodes "behind" it. Other results could be had by filtering the other interface.

To monitor and control the bridge you have created, use the [brconfig\(8\)](#) command, which can also be used to create a bridge after boot.

## Tips on bridging

- It is HIGHLY recommended that you filter on only one interface. While it is possible to filter on both, you really need to understand this very well to do it right.
- By using the *blocknonip* option of [brconfig\(8\)](#) or in [bridgename.bridge0](#), you can prevent non-IP traffic (such as IPX or NETBEUI) from slipping around your filters. This may be important in some situations, but you should be aware that bridges work for all kinds of traffic, not just IP.
- Bridging requires that the NICs be in a "Promiscuous mode" -- they listen to ALL network traffic, not just that directed at the interface. This will put a higher load on the processor and bus than one might expect. Some NICs don't work properly in this mode, the TI ThunderLAN chip ([tl\(4\)](#)) is an example of a chip that won't work as part of a bridge.

[\[FAQ Index\]](#) [\[To Section 5 - Building the System from Source\]](#) [\[To Section 7 - Keyboard and Display Controls\]](#)



[www@openbsd.org](mailto:www@openbsd.org)

\$OpenBSD: faq6.html,v 1.178 2003/09/09 02:08:41 nick Exp \$



[\[FAQ Index\]](#) [\[To Section 6 - Networking\]](#) [\[To Section 8 - General Questions\]](#)

## 7 - Keyboard and Display Controls

---

### Table of Contents

- [7.1 - How do I remap the keyboard? \(wscons\)](#)
  - [7.2 - Is there gpm or the like in OpenBSD?](#)
  - [7.3 - How do I clear the console each time a user logs out?](#)
  - [7.4 - Accessing the console scrollbar buffer. \(alpha/macppc/i386\)](#)
  - [7.5 - How do I switch consoles? \(i386\)](#)
  - [7.6 - How can I use a console resolution of 80x50? \(i386\)](#)
  - [7.7 - How do I use a serial console?](#)
  - [7.8 - How do I blank my console? \(wscons\)](#)
- 

### 7.1 - How do I remap the keyboard? (*wscons*)

The ports that use the [wscons\(4\)](#) console driver: [alpha](#), [hppa](#), [i386](#), [macppc](#), [sparc](#), and [sparc64](#).

With [wscons\(4\)](#) consoles, most options can be controlled using the [wsconsctl\(8\)](#) utility. For example, to change keymappings with [wsconsctl\(8\)](#) one would execute the following:

```
# wsconsctl -w keyboard.encoding=uk
```

In the next example, we will remap "Caps Lock" to be "Control L":

```
# wsconsctl -w keyboard.map+="keysym Caps_Lock = Control_L"
```

### 7.2 - Is there gpm or the like in OpenBSD?

For the [alpha](#) and [i386](#) platforms, OpenBSD provides [wsmoused\(8\)](#), a port of FreeBSD's [moused\(8\)](#). It can be enabled automatically at startup by editing the appropriate line in [rc.conf\(8\)](#).

### 7.3 - Clearing the console each time a user logs out.

To do this you must add a line in [/etc/gettytab\(5\)](#). Change the current section:

```
P|Pc|Pc console:\
:np:sp#9600:
```

adding the line ":cl=\E[H\E[2J:" at the end, so that it ends up looking like this:

```
P|Pc|Pc console:\
:np:sp#9600:\
:cl=\E[H\E[2J:
```

## 7.4 - Accessing the Console Scrollback Buffer (*i386, some Alpha*)

On some platforms, OpenBSD provides a console scrollback buffer. This allows you to see information that has already scrolled past your screen. To move up and down in the buffer, simply use the key combinations [SHIFT]+[PGUP] and [SHIFT]+[PGDN].

The default scrollback buffer, or the number of pages that you can move up and view, is 8. This is a feature of the [vga\(4\)](#) driver, so it will not work without a VGA card on any platform (many Alpha systems have TGA video).

## 7.5 - How do I switch consoles? (*i386, some Alpha*)

On i386 and Alpha systems with [vga\(4\)](#) cards, OpenBSD provides six virtual terminals by default, /dev/ttyC0 through /dev/ttyC5. ttyC4 is reserved for use by the X Window system, leaving five text consoles. You can switch between them using [CTRL]+[ALT]+[F1], [CTRL]+[ALT]+[F2], [CTRL]+[ALT]+[F3], [CTRL]+[ALT]+[F4] and [CTRL]+[ALT]+[F6].

The X environment uses ttyC4, [CTRL]+[ALT]+[F5]. When using X, the [CTRL]+[ALT]+[Fn] keys will take you to the text screens; [CTRL]+[ALT]+[F5] will take you back to the graphical environment.

If you wish to have more than the default number of virtual consoles, use the [wsconscfg\(8\)](#) command to create screens for ttyC6, ttyC7 and above. For example:

```
wsconscfg -t 80x25 6
```

will create a virtual terminal for ttyC6, accessed by [CTRL]+[ALT]+[F7]. Don't forget to add this command to your [rc.local\(8\)](#) file if you want the extra screen the next time you boot the computer.

Note that you will not get a "login:" prompt on the newly-created virtual console unless you set it to "on" in [/etc/ttys\(5\)](#), and either reboot or send [init\(8\)](#) a HUP signal using [kill\(1\)](#).

## 7.6 - How do I use a console resolution of 80x50? (*i386*)

i386 users normally get a console screen of 25 lines of 80 characters. However, many VGA video cards are capable of displaying a higher text resolution of 50 lines of 80 characters.

First, a font that supports the desired resolution must be loaded using the [wsfontload\(8\)](#) command. The standard 80x25 text screen

uses 8x16 pixel fonts; to double the number of lines we will have to use 8x8 pixel fonts.

After that, we will have to delete and recreate a [virtual console](#) at the desired screen resolution, using the [wsconscfg\(8\)](#) command.

This can be done automatically at boot by adding the following lines to the end of your [rc.local\(8\)](#) file:

```
wsfontload -h 8 -e ibm /usr/share/misc/pcvtfonts/vt2201.808
wsconscfg -dF 5
wsconscfg -t 80x50 5
```

As with any modification to your system configuration, it is recommended you spend some time with the man pages to understand what these commands do.

The first line above loads the 8x8 font. The second line deletes screen 5 (which would be accessed by [ CTRL ]+[ ALT ]+[ F6 ]). The third line creates a new screen 5 with 50 lines of 80 characters each. If you do this, you will see your primary screen, and the other three default virtual consoles, come up in the standard 80x25 mode, but a new screen 5 at 80x50 accessible through [ CTRL ]+[ ALT ]+[ F6 ].

Remember that [ CTRL ]+[ ALT ]+[ F1 ] is screen 0 (ttyC0). If you wish to alter other screens, simply repeat the delete and add screen steps for whichever screens you want running at the 80x50 resolution.

You should avoid changing screen 4 (ttyC4, [ CTRL ]+[ ALT ]+[ F5 ]), which is used by X as a graphical screen. It is also not possible to change the resolution of the primary console device (i.e., ttyC0).

As one might expect, all these commands can also be entered at the command prompt, as root, or (better) using [sudo\(8\)](#).

**Note: this will not work on all video cards.** Unfortunately, not all video cards support the uploaded fonts that [wscons\(4\)](#) requires to achieve the 80x50 text mode. In these cases, you might wish to consider running X.

## 7.7 - How do I use a serial console?

There are many reasons you may wish to use a serial console for your OpenBSD system:

- Recording console output (for documentation).
- Remote management.
- Easier maintenance of a large quantity of machines
- Providing a useful dmesg from machines which might otherwise be difficult to get one from.
- Providing an accurate "trace" and "ps" output if your system crashes so developers can have a chance to fix the problem.

OpenBSD supports serial console on most platforms, however details vary greatly between platforms.

Note that serial interfacing is NOT a trivial task -- you will often need unusual cables, and ports are not standardized between machines, in some cases, not even consistent on one machine. It is assumed you know how to select the appropriate cable to go between your computer and the device acting as your serial terminal. A full tutorial on serial interfacing is beyond the scope of this article, however, we offer one hint: just because the ends plug in doesn't mean it will work.

### ***/etc/ttys change***

There are two parts to getting a functional serial console on an OpenBSD system. First, you must have OpenBSD to use your serial

port as a console for status and single user mode. This part is very platform dependent. Second, you must enable the serial port to be used as an interactive terminal, so a user can log into it when running multi-user. This part is fairly similar between platforms, and is detailed here.

Terminal sessions are controlled by the [/etc/ttys](#) file. Before OpenBSD will give you a "login:" prompt at a device, it has to be enabled in [/etc/ttys](#), after all, there are other uses for a serial port other than for a terminal. In platforms which typically have an attached keyboard and screen as a console, the serial terminal is typically disabled by default. We'll use the i386 platform as an example. In this case, you must edit the line that reads:

```
tty00    "/usr/libexec/getty std.9600"    unknown off
```

to read:

```
tty00    "/usr/libexec/getty std.9600"    vt100    on secure
```

Here, `tty00` is the serial port we are using as a console. The "on" activates the [getty](#) for that serial port so it can a "login:" prompt will be presented, the "secure" permits a root (uid 0) login at this console (which may or may not be what you desire), and the "9600" is the terminal baud rate. Note that you can use a serial console for install without doing this step, as the system is running in single user mode, and not using [getty](#) for login.

On some platforms and some configurations, you must bring the system up in single user mode to make this change if a serial console is all you have available.

## i386

To direct the boot process to use the serial port as a console, create or edit your [/etc/boot.conf](#) file to include the line:

```
set tty com0
```

assuming you want the first serial port to be used as your console. The default baud rate is 9600bps, this can be changed with a [/etc/boot.conf](#) line using the `stty` option. This file is put on your boot drive, which could also be your install floppy, or the command can be entered at the `boot>` prompt from the [OpenBSD second-stage boot loader](#) for a one-time (or first time) serial console usage.

### i386 notes:

- OpenBSD numbers the serial ports starting at `tty00`, DOS/Windows labels them starting at `COM1`. So, keep in mind `tty02` is `COM3`, not `COM2`
- Some systems may be able to operate without a video card in the machine, but certainly not all -- many systems consider this an error condition. Some machines will even refuse to work easily without a keyboard attached.
- Some i386 systems are capable of using a serial port as the console device. Your results may vary -- this port may not be available to the operating system once booted, thus requiring monitoring using TWO serial ports.
- PC compatible computers are not designed to be run from a serial console, unlike some other platforms. Even those systems that support a serial console usually have it as a BIOS configuration option -- and should the configuration information get corrupted, you will find the system looking for a standard monitor and keyboard again. You generally must have some way to get a monitor and keyboard to your i386 systems in an emergency.
- You will need to edit [/etc/ttys](#) as [above](#).

## SPARC and UltraSPARC

These machines are designed to be completely maintainable with a serial console. Simply remove the keyboard from the machine,

and the system will run serial.

## SPARC and UltraSPARC notes

- The serial ports on a SPARC are labeled *ttya*, *ttyb*, etc.
- Unlike some other platforms, it is not necessary to make any changes to */etc/ttys* to use a serial console.
- The SPARC/UltraSPARC systems interpret a BREAK signal on the console port to be the same as a STOP-A command, and kicks the system back to the Forth prompt, stopping any application and operating system at that point. This is handy when desired, but unfortunately, some serial terminals at power-down and some RS-232 switching devices send something the computer interprets as a break signal, halting the machine. Test before you go into production.
- If you have a keyboard and monitor attached, you can still force the serial console to be used instead by using the following commands at the `ok` prompt:

```
ok setenv input-device ttya
ok setenv output-device ttya
ok reset
```

If the keyboard and monitor (`ttyC0`) are active in */etc/ttys* ([above](#)), you can use the keyboard and monitor in X. Some combinations of SPARC hardware have trouble with the keyboard when doing this in OpenBSD 3.2 and earlier, but should work well in OpenBSD 3.3.

## MacPPC

The MacPPC machines are configured for a serial console through OpenFirmware. Use the commands:

```
ok setenv output-device scca
ok setenv input-device scca
ok reset-all
```

Set your serial console to 57600bps, 8N1.

## MacPPC notes

- Unfortunately, serial console is not directly possible on most MacPPCs. While most of these machines do have serial hardware, it isn't accessible outside the machine. Fortunately, a few companies offer add-on devices for several Macintosh models which will make this port available for use as a serial console (or other uses). Use your favorite search engine and look for "Macintosh internal serial port".
- You will have to change `tty00` in */etc/ttys* to `on` and set the speed to 57600 instead of the default of 9600 as detailed [above](#) in single user mode before booting multi-user and having the serial console functional.

## Mac68k

Serial console is selected in the *Booter* program, under the "Options" pull-down menu, then "Serial Ports". Check the "Serial Console" button, then choose the Modem or Printer port. You will need a Macintosh modem or printer cable to attach to the Mac's serial ports. If you wish to have this as default, tell the Booter program to save your options.

## Mac68k Notes

- The modem port is *tty00*, the printer port is *tty01*.

- The Mac68k doesn't turn on its serial port until called upon, so your breakout box may not show any signals on the Mac's serial port until the OpenBSD boot process has started.
- You will have to enable the port (*tty00* or *tty01*) as indicated [above](#).

## 7.8 - How do I blank my console? (wscons)

If you wish to blank your console after a period of inactivity without using X, you can alter the following [wscons\(4\)](#) variables:

- **display.vblank** set to `on` will disable the vertical sync pulse, which will cause many monitors to go into an "energy saver" mode. This will require more time to bring the screen back on, but will reduce energy consumption and heat production of newer monitors. When set to `off`, the display will blank, but the monitor will still be receiving the normal horizontal and vertical sync pulses, so the unblanking will be almost instant.
- **display.screen\_off** determines the blanking time in thousandths of a second, i.e., 60000 would set the timeout to one minute.
- **display.kbdact** determines if keyboard activity will restore the blanked screen. Usually, this is desirable.
- **display.outact** determines if screen output will restore the blanked screen.

You can set these variables at the command line using the [wsconctl\(8\)](#) command:

```
# wsconctl -w display.screen_off=60000
display.screen_off -> 60000
```

or set them permanently by editing [/etc/wsconctl.conf](#) so these changes take place at next boot:

```
display.vblank=on           # enable vertical sync blank
display.screen_off=600000   # set screen blank timeout to 10 minutes
display.kbdact=on          # Restore screen on keyboard input
display.outact=off         # Restore screen on display output
```

The blanker is activated when either `display.kbdact` or `display.outact` is set to "on".

[\[FAQ Index\]](#) [\[To Section 6 - Networking\]](#) [\[To Section 8 - General Questions\]](#)



[www@openbsd.org](mailto:www@openbsd.org)

\$OpenBSD: faq7.html,v 1.53 2003/07/23 01:53:01 nick Exp \$

# OpenBSD

[\[FAQ Index\]](#) [\[To Section 7 - Keyboard and Display controls\]](#) [\[To Section 9 - Migrating from Linux\]](#)

## 8 - General Questions

---

### Table of Contents

- [8.1 - I forgot my root password..... What do I do!](#)
  - [8.2 - X won't start, I get lots of error messages](#)
  - [8.3 - What is CVS, and how do I use it?](#)
  - [8.4 - What is the ports tree?](#)
  - [8.5 - What are packages?](#)
  - [8.6 - Should I use Ports or Packages?](#)
  - [8.8 - Is there any way to use my floppy drive if it's not attached during boot?](#)
  - [8.9 - OpenBSD Bootloader \(i386 specific\)](#)
  - [8.10 - Using S/Key on your OpenBSD system](#)
  - [8.12 - Does OpenBSD support SMP?](#)
  - [8.13 - I sometimes get Input/output error when trying to use my tty devices](#)
  - [8.14 - What web browsers are available for OpenBSD?](#)
  - [8.15 - How do I use the mg editor?](#)
  - [8.16 - ksh\(1\) does not appear to read my .profile!](#)
  - [8.17 - Why does my /etc/motd file get written over when I modified it?](#)
  - [8.18 - Why does www.openbsd.org run on Solaris?](#)
  - [8.19 - I'm having problems with PCI devices being detected](#)
  - [8.20 - Antialiased and TrueType fonts in XFree86](#)
  - [8.21 - Does OpenBSD support any journaling filesystems?](#)
  - [8.22 - Reverse DNS or Why is it taking so long for me to log in?](#)
  - [8.23 - Why do the OpenBSD web pages not conform to HTML4/XHTML?](#)
  - [8.24 - Why is my clock off by twenty-some seconds?](#)
- 

### 8.1 - I forgot my root password, what do I do now?

A few steps to recovery

1. Boot into single user mode. For i386 arch type boot -s at the boot prompt.
2. mount the drives.
 

```
# fsck -p / && mount -uw /
```
3. If /usr is not the same partition that / is (and it shouldn't be) then you will need to mount it, also
 

```
# fsck -p /usr && mount /usr
```
4. run [passwd\(1\)](#)
5. boot into multiuser mode... and *remember* your password!

### 8.2 - X won't start, I get lots of error messages

If you have X completely set up and you are using an XF86Config that you know works then the problem most likely lies in the machdep.allowaperture. You also need to make sure that:

```
option APERTURE
```

is in your kernel configuration. [It is already in the GENERIC kernel]

Then you need to edit `/etc/sysctl.conf` and set `machdep.allowaperture=2`. This will allow X to access the aperture driver. This would already be set if you said that you would be running X when asked during the install. OpenBSD requires for all X servers that the aperture driver be set, because it controls access to the I/O ports on video boards.

For other X problems on the i386, consult the XFree86 Online Documentation at <http://www.xfree86.org/support.html>.

## 8.3 - What is CVS? and How do I use it?

CVS is the tool that OpenBSD project uses to control changes to the source code. CVS stands for Concurrent Versions System. You can read more about CVS at <http://www.cvshome.org/>. CVS can be used by the end user to keep up to date with source changes, and changes in the ports tree. CVS makes it extremely simple to download the source via one of the many CVS mirrors for the project.

### How to initially setup your CVS environment

You can retrieve the sources from one of the OpenBSD AnonCVS servers. These servers are listed on <http://www.openbsd.org/anoncv.html>. Once you have chosen a server you need to choose which module you are going to retrieve. There are three main modules available for checkout from the CVS tree. These are:

- *src* - The src module has the complete source code for OpenBSD. This includes userland and kernel sources.
- *ports* - The ports module holds all you need to have the complete OpenBSD ports tree. To read more on the OpenBSD ports tree, read [FAQ 8, Ports](#) of the OpenBSD FAQ.
- *XF4* - The XF4 module contains the source to compile XFree 4.

Now that you have decided which module that you wish to retrieve, there is one more step left before you can retrieve it. You must decide which method to use. CVS by default retrieves files using [ssh\(1\)](#), but some AnonCVS servers allow for the use of [rsh](#). For those of you behind a firewall there are also the options of pserver and some AnonCVS servers run ssh on port 2022. Be sure to check <http://www.openbsd.org/anoncv.html> for which servers support what protocols. Next I will show how to do a simple source checkout. Here I will be using an AnonCVS server located in the U.S., but remember that if you are outside of the U.S you need to use a server that is located nearby. There are many AnonCVS servers located throughout the world, so choose one nearest you. I will also be using ssh to retrieve the files.

```
$ export CVSROOT=anoncv@anoncv.usa.openbsd.org:/cvs
$ cvs get src
Warning: Remote host denied X11 forwarding, perhaps xauth program could not be run on the server side.
cvs checkout: in directory src:
cvs checkout: cannot open CVS/Entries for reading: No such file or directory
cvs server: Updating src
U src/Makefile
[snip]
```

Notice here also that I set the CVSROOT environment variable. This is the variable that tells [cvs\(1\)](#) which AnonCVS server to use. This can also be specified using the *-d* option. For example:

```
$ cvs -d anoncv@anoncv.usa.openbsd.org:/cvs get src
```

These commands should be run in */usr*, which will then create the directories of */usr/src*, */usr/ports*, and */usr/www*. Depending, of course, on which module you checkout. You can download these modules to anywhere, but if you wanted to do work with them (ie make build), it is expected that they be at the place above.

### Keeping your CVS tree up-to-date

Once you have your initial tree setup, keeping it up-to-date is the easy part. You can update your tree at any time you choose, some AnonCVS servers update more often than others, so again check <http://www.openbsd.org/anoncv.html>. In this example I will be updating my www module from anoncv.usa.openbsd.org. Notice the *-q* option that I use, this makes the output not so verbose coming from the server.

```
$ echo $CVSROOT
anoncv@anoncv.usa.openbsd.org:/cvs
$ cvs -q up -Pd www
Warning: Remote host denied X11 forwarding, perhaps xauth program could not be run on the server side.
U www/want.html
M www/faq/faq8.html
ericj@oshibana:~>
```

### Other cvs options

For some, bandwidth and time are serious problems when updating repositories such as these. So CVS has a *-z[1-9]* option which uses gzip to compress the data. To use it, do *-z[compression-level]*, for instance, *-z3* for a compression level of 3.

## 8.4 - What is the ports tree?

The ports tree is a set of Makefiles that download, patch, configure and install userland programs so you can run them in OpenBSD environment without having to do all that by hand. You can get the ports tree from any of the OpenBSD FTP servers in */pub/OpenBSD/3.3/ports.tar.gz*. The most recent ports are available via the 'ports' cvs tree, or */pub/OpenBSD/snapshots/ports.tar.gz*. For most of you however, packages will be a much better option. Packages are created from ports and are already compiled and ready to use. To read more on packages read [FAQ 8, Packages](#).

## Important note about keeping your system and ports in sync

OpenBSD has three "active" versions at any point in time:

- [Release](#): What is on the CD.
- [Stable](#): Release, plus security and reliability enhancements
- [Current](#): The development version of OpenBSD.

### DO NOT mix versions of Ports and OpenBSD!

If your system is Release, use the Release version of the ports tree. Don't try to use a -Current version of the Ports tree on a -Release or -Stable system. Not only is it not likely to work, you will irritate people when you ask for help about why "nothing seems to work!" Note that there is a [-Stable](#) branch of the Ports tree as well, where critical fixes to -Release ports will be made.

Yes, this really does mean a wonderful new port will not typically work on your "older" system -- even if that system was -current just a few weeks ago.

If you do not have the ports tree installed, you can download it via any of OpenBSD's [FTP servers](#), or of course, from the [CD-ROM](#). The file is `ports.tar.gz`, and you want to untar this in the `/usr` directory, which will create `/usr/ports`, and all the directories under it. For example:

```
$ ftp ftp://ftp.openbsd.org/pub/OpenBSD/3.3/ports.tar.gz
$ sudo cp ports.tar.gz /usr
$ cd /usr; sudo tar xzf ports.tar.gz
```

A snapshot of the ports tree is also created daily and can be downloaded from any of the [OpenBSD FTP servers](#) as `/pub/OpenBSD/snapshots/ports.tar.gz`. If you are installing a snapshot of OpenBSD, you should use a matching snapshot of ports. Again, make sure you keep your ports tree and your OpenBSD system in sync.

## What ports are available? How do i find them?

Use the ports tree to search for keywords. To do this use `make search key="searchkey"`. Here is an example of a search for 'samba':

```
$ make search key="samba"
[...snip...]
Port:   amanda-client-2.4.2.2
Path:   misc/amanda,-client
Info:   network-capable tape backup (client only)
Maint:  Tom Schutter <t.schutter@att.net>
Index:  misc
L-deps:
B-deps: :devel/gmake gnuplot-*:math/gnuplot gtar-*:archivers/gtar samba-*:net/samba/stable
R-deps:
Archs:  any

Port:   samba-2.2.8a
Path:   net/samba/stable
Info:   SMB and CIFS client and server for UNIX
Maint:  The OpenBSD ports mailing-list <ports@openbsd.org>
Index:  net
L-deps: popt::devel/popt
B-deps: :devel/autoconf/2.13 :devel/metaauto
R-deps:
Archs:  any
[...snip...]
```

## Installing Ports

Ports are set up to be EXTREMELY easy to make and install. Here is an example showing how to install the X11 program `xfig`. You'll notice the dependencies are automatically detected and completed.

First you need to `cd` to the dir of the program you want. If you are searching for a program, you can either update your locate database, or use the search function talked about above. Once you are in the dir of the program you want, you can just type `make install`. For example.

```
$ sudo make install
==> Checking files for xfig-3.2.4
>> xfig.3.2.4.full.tar.gz doesn't seem to exist on this system.
>> Attempting to fetch /usr/ports/distfiles/xfig.3.2.4.full.tar.gz from http://www.xfig.org/xfigdist/.
100% |*****| 5042 KB 00:31
>> Checksum OK for xfig.3.2.4.full.tar.gz. (sha1)
```

```

====> xfig-3.2.4 depends on: jpeg.62 - jpeg.62 missing...
====> Verifying install for jpeg.62 in graphics/jpeg
====> Checking files for jpeg-6b
>> jpegsrvc.v6b.tar.gz doesn't seem to exist on this system.
>> Attempting to fetch /usr/ports/distfiles/jpegsrvc.v6b.tar.gz from ftp://ftp.uu
.net/graphics/jpeg/.
'EPSV': command not understood.
100% |*****| 598 KB 00:06
>> Checksum OK for jpegsrvc.v6b.tar.gz. (shal)
====> Extracting for jpeg-6b
====> Patching for jpeg-6b
====> Configuring for jpeg-6b
checking for gcc... cc
checking whether the C compiler (cc -O2 ) works... yes
checking whether the C compiler (cc -O2 ) is a cross-compiler... no
checking whether we are using GNU C... yes
[...snip...]

```

## Using Flavors

Many of the applications in the ports tree support different install options, called *flavors*. If a port comes in multiple flavors, you can use these options simply by setting an environment variable before you compile the port. If multiple features are needed, the FLAVOR variable can be set to a space-delimited list of the supported and desired flavors. Currently, many ports have flavors that include database support, support for systems without X, or network additions like SSL and IPv6.

```

$ pwd
/usr/ports/net/mtr
$ make show=FLAVORS
no_x11
$ env FLAVOR="no_x11" make
====> mtr-0.49-no_x11 depends on: gmake-3.80 - not found
====> Verifying install for gmake-3.80 in devel/gmake
====> Checking files for gmake-3.80
>> make-3.80.tar.gz doesn't seem to exist on this system.
>> Attempting to fetch /usr/ports/distfiles/make-3.80.tar.gz from ftp://ftp.gnu.
org/gnu/make/.
Unknown command.
100% |*****| 1183 KB 00:07
>> Checksum OK for make-3.80.tar.gz. (shal)
[...snip...]
$ sudo env FLAVOR="no_x11" make install
====> Faking installation for mtr-0.49-no_x11
[...snip...]
====> Building package for mtr-0.49-no_x11
Creating package /usr/ports/packages/i386/All/mtr-0.49-no_x11.tgz
Using SrcDir value of /usr/ports/net/mtr/w-mtr-0.49-no_x11/fake-i386-no_x11/usr/
local
Creating gzip'd tar ball in '/usr/ports/packages/i386/All/mtr-0.49-no_x11.tgz'
====> Installing mtr-0.49-no_x11 from /usr/ports/packages/i386/All/mtr-0.49-no_a
x11.tgz

```

## Listing Installed ports/packages

You can see a list of both ports and packages by using the pkg\_info command.

```

$ /usr/sbin/pkg_info
zsh-4.0.6      The Z shell.
screen-3.9.13 A multi-screen window manager.
emacs-21.2    GNU editing macros.
tcsh-6.12.00  An extended C-shell with many useful features.
bash-2.05b    The GNU Borne Again Shell.
zip-2.3       Create/update ZIP files compatible with pkzip.
ircII-20030314 An enhanced version of ircII, the Internet Relay Chat client
ispell-3.2.06 An interactive spelling checker.
tin-1.4.6     TIN newsreader (termcap based)
procmail-3.22 A local mail delivery agent.
strobe-1.06   Fast scatter/gather TCP port scanner
lsof-4.67     Lists information about open files.
ntp-4.1.74    Network Time Protocol Implementation.
ncftp-3.1.5p0 ftp replacement with advanced user interface
nmh-1.0.4p1   The New MH mail handling program
bzip2-1.0.2   A block-sorting file compressor

```

## Other Information

More information about the ports can be found in the [ports\(7\)](#) man page and on the [Ports page](#).

Our ports tree is constantly being expanded, and if you would like to help please see: <http://www.openbsd.org/porting.html>.

## 8.5 - What are packages?

Packages are the precompiled binaries of some of the most used programs. They are ready for use on an OpenBSD system. Again, like the ports, packages are very easy to maintain and update. Packages are constantly being added so be sure to check each release for additional packages.

Here is a list of tools used in managing packages.

- [pkg\\_add\(1\)](#) - a utility for installing software package distributions
- [pkg\\_create\(1\)](#) - a utility for creating software package distributions
- [pkg\\_delete\(1\)](#) - a utility for deleting previously installed software package distributions
- [pkg\\_info\(1\)](#) - a utility for displaying information on software packages

### Where to find packages

If you are a smart user and bought an [OpenBSD CD set](#), then packages can be found on one of the three CDs, depending on your architecture. If you don't have an OpenBSD CD in your possession you can download packages from any of the ftp mirrors. You can get a list of mirrors <http://www.openbsd.org/ftp.html>. Packages are located at */pub/OpenBSD/3.3/packages* from there packages are broken down depending on architecture.

### Installing Packages

To install packages, the utility [pkg\\_add\(1\)](#) is used. [pkg\\_add\(1\)](#) is an extremely easy utility to use, in the following two examples [pkg\\_add\(1\)](#) will be used to install a package. The first example will show [pkg\\_add\(1\)](#) installing a package that resides on a local disk, the second example will show an installation of a package via ftp. In both examples screen-3.9.13 will be installed.

Installing via local disk

```
$ sudo pkg_add -v screen-3.9.13.tgz
Requested space: 749864 bytes, free space: 2239117312 bytes in /var/tmp/instmp.cpsHA27596
Running install with PRE-INSTALL for `screen-3.9.13'
extract: Package name is screen-3.9.13
extract: CWD to /usr/local
extract: /usr/local/bin/screen-3.9.13
extract: execute 'ln -sf screen-3.9.13 /usr/local/bin/screen'
extract: /usr/local/man/man1/screen.1
extract: /usr/local/info/screen.info
extract: execute '[ -f /usr/local/info/dir ] || sed -ne '1,/Menu:/p' /usr/share/info/dir > /usr/local/info/dir'
extract: execute 'install-info /usr/local/info/screen.info /usr/local/info/dir'
extract: /usr/local/lib/screen/screencap
extract: /usr/local/lib/screen/screenrc
extract: CWD to .
Runningmtree for `screen-3.9.13'
mtree -q -U -f +MTREE_DIRS -d -e -p /usr/local
Running install with POST-INSTALL for `screen-3.9.13'

+-----+
| The file /etc/screenrc has been created on your system.
| You may want to verify/edit its contents
|
| The file /usr/local/lib/screen/screencap contains a
| termcap like description of the screen virtual terminal.
| You may use it to update your terminal database.
| See termcap\(5\).
+-----+

Attempting to record package into `/var/db/pkg/screen'
Package `screen-3.9.13' registered in `/var/db/pkg/screen-3.9.13'
```

In this example the `-v` flag was used to give a more verbose output. This option is not needed but is helpful for debugging and was used here to give a little more insight into what [pkg\\_add\(1\)](#) is actually doing. Notice however, that there are some valid messages given out mentioning */etc/screenrc*. Messages like this will be given to you whether or not you use the `-v` flag.

Installing via ftp

```
$ sudo pkg_add ftp://ftp.openbsd.org/pub/OpenBSD/3.3/packages/i386/screen-3.9.13.tgz
```

```
>>> ftp -o - ftp://ftp.openbsd.org/pub/OpenBSD/3.3/packages/i386/screen-3.9.13.tgz

+-----+
| The file /etc/screenrc has been created on your system.
| You may want to verify/edit its contents
|
| The file /usr/local/lib/screen/screencap contains a
| termcap like description of the screen virtual terminal.
| You may use it to update your terminal database.
| See termcap(5).
+-----+
```

In this example you can see that I installed the *i386* package. You should substitute *i386* (above) with your architecture. Notice: Not all architectures have the same packages. Some ports don't work on certain architectures. In this example the `-v` flag wasn't used, so only `NEEDED` messages are shown.

## Viewing and Deleting Installed Packages

The utility [pkg\\_info\(1\)](#) is used to view a list of packages that are already installed on your system. This is usually needed to find out the correct name of a package before you remove that package. To see what packages are installed on your system simple use:

```
$ pkg_info
mpeg123-0.59r      mpeg audio 1/2 layer 1, 2 and 3 player
nmap-3.00          port scanning large networks
ircII-20030314    enhanced version of ircII (internet relay chat)
screen-3.9.13     multi-screen window manager
unzip-5.50        extract, list & test files in a ZIP archive
ntp-4.1.74        Network Time Protocol implementation
icb-5.0.9p1       Internet CB - mostly-defunct chat client
```

To delete a package, simple take the proper name of the package as shown by `pkg_info(1)` and use [pkg\\_delete\(1\)](#) to remove the package. In the below example, the `screen` package is being removed. Notice that on some occasions there are instructions of extra objects that need to be removed that `pkg_delete(1)` did not remove for you. As with the `pkg_add(1)` utility, you can use the `-v` flag to get more verbose output.

```
$ sudo pkg_delete screen-3.9.13

+-----+
| To completely deinstall the screen-3.9.13 package you need to perform
| this step as root:
|
|           rm -f /etc/screenrc
|
| Do not do this if you plan on re-installing screen-3.9.13
| at some future time.
+-----+
```

## 8.6 - Should I use Ports or Packages?

In general, you are **HIGHLY** advised to use [packages](#) over building an application from [ports](#). The OpenBSD ports team considers packages to be the goal of their porting work, not the ports themselves.

Building a complex application from source is not trivial. Not only must the application be compiled, but the tools used to build it must be built. Unfortunately, OpenBSD, the tools, and the application are all evolving, and often, getting all the pieces working together is a challenge. Once everything works, a revision in any of the pieces the next day could render it broken. Every [six months](#), as a [new release](#) of OpenBSD is made, an effort is made to test the building of every port on every platform, but during the development cycle it is likely that some ports will break.

In addition to having all the pieces work together, there is just the matter of time and resources required to compile some applications from source. A common example is [CVSup](#), a tool commonly used to [track the OpenBSD source tree](#). To install CVSup on a moderately fast system with a good Internet connection may take only about ten seconds -- the time required to download and unpack a single 511kB package file. In contrast, building CVSup on the same machine from source is a huge task, requiring many tools and bootstrapping a compiler, takes almost half an hour on the same machine. Other applications, such as [Mozilla](#) or [KDE](#) may take hours and huge amounts of disk space and RAM/swap to build. Why go through this much time and effort, when the programs are already compiled and sitting on your [CD-ROM](#) or [FTP mirror](#), waiting to be used?

Of course, there are a few good reasons to use ports over packages in some cases:

- Distribution rules prohibit OpenBSD from distributing a package.
- You wish to modify or debug the application or study its source code.
- You need a FLAVOR of a port that is not built by the OpenBSD ports team.
- You wish to alter the directory layout (i.e., modifying PREFIX or SYSCONFDIR)

However, for most people and most applications, using packages is a far easier, and is the recommended way of adding applications to OpenBSD.

## 8.8 - Is there any way to use my floppy drive if it's not attached during boot?

Sure. You need to add "flags 0x20" at the end of the fd\* entry and recompile your kernel. The line should be read:

```
fd*      at fdc? drive ? flags 0x20
```

After that you would be able to use the floppy drive all the times. It doesn't matter if you plugged it in after boot.

## 8.9 - Boot time Options - Using the OpenBSD bootloader

When booting your OpenBSD system, you have probably noticed the boot prompt.

```
boot>
```

For most people, you won't have to do anything here. It will automatically boot if no commands are given. But sometimes problems arise, or special functions are needed. That's where these options will come in handy. To start off, you should read through the [boot\(8\)](#) man page. Here we will go over the most common used commands for the bootloader.

To start off, if no commands are issued, the bootloader will automatically try to boot **/bsd**. If that fails it will try **/obsd**, and if that fails, it will try **/bsd.old**. You can specify this by hand by typing:

```
boot> boot wd0a:/bsd
```

or

```
boot> b /bsd
```

This will work if device wd0a is configured as your root device.

Here is a brief list of options you can use with the OpenBSD kernel.

- **-a** : This will allow you to specify an alternate root device after booting the kernel.
- **-c** : This allows you to enter the boot time configuration. Check the [Boot Time Config](#) section of the faq.
- **-s** : This is the option to boot into single user mode.
- **-d** : This option is used to dump the kernel into ddb. Keep in mind that you must have DDB built into the kernel.

These are entered in the format of: **boot [ image [-acds]]**

For further reading you can read [boot\\_i386\(8\)](#) man page

## 8.10 - S/Key

S/Key is a "one-time password" scheme. This allows for one-time passwords for use on un-secured channels. This can come in handy for those who don't have the ability to use ssh or any other encrypted channels. OpenBSD's S/Key implementation can use a variety of algorithms as the one-way hash. The following algorithms are available:

- [md4](#)
- [md5](#)
- [sha1](#)
- [rmd160](#).

### Setting up S/Key - The first steps

To start off the directory `/etc/skey` must exist. If this directory is not in existence, have the super-user create it. This can be done simply by doing:

```
# mkdir /etc/skey
```

Once that directory is in existence, you can initialize your S/Key. To do this you will have to use [skeyinit\(1\)](#). With `skeyinit(1)`, you will first be prompted for your password to the system. This is the same password that you used to log into the system. Running `skeyinit(1)` over an insecure channel is completely not recommended, so this should be done over a secure channel (such as ssh) or the console. Once you have authorized yourself with your system password you will be asked for yet another password. This password is the S/Key *secret password*, and is **NOT** your system password. Your secret password must be at least 10 characters. We suggest using a memorable phrase containing several words as the secret password. Here is an example user being added.

```

$ skeyinit ericj
[Adding ericj]
Reminder - Only use this method if you are directly connected
or have an encrypted channel. If you are using telnet
or rlogin, exit with no password and use skeyinit -s.
Enter secret password:
Again secret password:

ID ericj skey is otp-md5 99 oshi45820
Next login password: HAUL BUS JAKE DING HOT HOG

```

One line of particular importance in here is *ID ericj skey is otp-md5 99 oshi45820*. This gives a lot of information to the user. Here is a breakdown of the sections and their importance.

- *otp-md5* - This shows which one-way was used to create your One-Time Password (otp).
- *99* - This is your sequence number. This is a number from 100 down to 1. Once it reaches one, another secret password must be created.
- *oshi45820* - This is your key.

But of more immediate importance is your password. Your password consists of 6 small words, combined together this is your password, spaces and all.

## Actually using S/Key to login.

By now your skey has been initialized, and you have your password. You're ready to login. Here is an example session using S/Key to login. Starting with OpenBSD 3.0, S/Key logins work differently. For OpenBSD 3.0 and above you append **:skey** to your login name. For versions of OpenBSD previous to 3.0 you use **s/key** for the password at which time you are prompted for your S/Key password (the exception to this is ftpd(8) which will always present an S/Key challenge for S/Key-enabled user prior to OpenBSD < 3.0). The examples below assume OpenBSD 3.0 or higher.

```

$ ftp localhost
Connected to localhost.
220 oshibana.shin.ms FTP server (Version 6.5/OpenBSD) ready.
Name (localhost:ericj): ericj:skey
331- otp-md5 96 oshi45820
331 S/Key Password:
230- OpenBSD 3.3 (GENERIC) #44: Sat Mar 29 13:22:05 MST 2003
230-
230- Welcome to OpenBSD: The proactively secure Unix-like operating system.
230-
230- Please use the sendbug(1) utility to report bugs in the system.
230- Before reporting a bug, please try to reproduce it with the latest
230- version of the code. With bug reports, please try to ensure that
230- enough information to reproduce the problem is enclosed, and if a
230- known fix for it exists, include that as well.
230-
230 User ericj logged in.
Remote system type is UNIX.
Using binary mode to transfer files.
ftp> quit
221 Goodbye.

```

Note that I appended ":skey" to my username. This tells ftpd that I want to authenticate using S/Key. Some of you might have noticed that my sequence number has changed to *otp-md5 96 oshi45820*. This is because by now I have used S/Key to login several times. But how do you get your password after you've logged in once? Well to do this, you'll need to know what sequence number you're using and your key. As you're probably thinking, how can you remember which sequence number you're on? Well this is simple, use [skeyinfo\(1\)](#), and it will tell you what to use. For example here, I need to generate another password for a login that I might have to make in the future. (remember I'm doing this from a secure channel).

```

$ skeyinfo
95 oshi45820

```

An even better way is to use **skeyinfo -v**, which outputs a command suitable to be run in the shell. For instance:

```

$ skeyinfo -v
otp-md5 95 oshi45820

```

Not only is *otp-md5* a description of the hash used, it is also an alternate name for the [skey\(1\)](#) command. So, the simplest way to generate the next S/Key password is simply:

```

$ `skeyinfo -v`
Reminder - Do not use this program while logged in via telnet or rlogin.
Enter secret password:
NOOK CHUB HOYT SAC DOLE FUME

```

Note the backticks in the above example.

I'm sure many of you won't always have a secure connection to create these passwords, and creating them over an insecure connection isn't feasible, so how can you create multiple passwords at one time? Well you can supply `skey(1)` with a number of how many passwords you want created. This can then be printed out and taken with you wherever you go.

```
$ otp-md5 -n 5 95 oshi45820
Reminder - Do not use this program while logged in via telnet or rlogin.
Enter secret password:
91: SHIM SET LEST HANS SMUG BOOT
92: SUE ARTY YAW SEED KURD BAND
93: JOEY SOOT PHI KYLE CURT REEK
94: WIRE BOGY MESS JUDE RUNT ADD
95: NOOK CHUB HOYT SAC DOLE FUME
```

Notice here though, that the bottom password should be the first used, because we are counting down from 100.

### Using S/Key with telnet(1), ssh(1), and rlogin(1)

Using S/Key with telnet(1), ssh(1), or rlogin(1) is done in pretty much the same fashion as with ftp--you simply tack ":skey" to the end of your username. Example:

```
$ telnet localhost
Trying 127.0.0.1...
Connected to localhost.
Escape character is '^'.

OpenBSD/i386 (oshihana) (tty2)

login: ericj:skey
otp-md5 98 oshi45821
S/Key Password: SCAN OLGA BING PUB REEL COCA
Last login: Thu Oct 7 12:21:48 on tty1 from 156.63.248.77
Warning: no Kerberos tickets issued.
OpenBSD 3.3 (GENERIC) #44: Sat Mar 29 13:22:05 MST 2003

Welcome to OpenBSD: The proactively secure Unix-like operating system.

Please use the sendbug(1) utility to report bugs in the system.
Before reporting a bug, please try to reproduce it with the latest
version of the code. With bug reports, please try to ensure that
enough information to reproduce the problem is enclosed, and if a
known fix for it exists, include that as well.

You have mail.
$
```

## 8.12 - Does OpenBSD support SMP? (Symmetric Multi-Processor)

Not at this time. Work is on-going, there is an [OpenBSD SMP project](#), though there is nothing usable yet, nor is there any time schedule for OpenBSD SMP support.

On most platforms, OpenBSD will run on an SMP system, but only utilizing one processor. The exception to this is the [SPARC](#) platform -- OpenBSD/sparc will sometimes require that extra MBus modules be removed for the system to boot. Multi-processor SPARC64 systems run as long as the base machine is [supported](#).

### How can I help?

- Write code. There is lots of work to do.
- Donate hardware. The goal of the OpenBSD SMP project is to support as many platforms as possible, including [SPARC](#), [SPARC64](#), [Alpha](#), [MacPPC](#) and of course, the [i386](#). Donations of [desired hardware](#) are welcome!
- Don't offer to "test". The SMP project is not part of the core OpenBSD project right now for a reason -- it isn't ready for production use yet, or even general "testing". Informing the developers that it didn't work on your hardware without code to make it work isn't useful at this point. [Send in your dmesg](#), if a developer sees something interesting in your hardware, they can contact you for testing.

## 8.13 - I get Input/output error when trying to use my tty devices

You need to use `/dev/cuaXX` for connections initiated from the OpenBSD system, the `/dev/ttyXX` devices are intended only for terminal or dial-in usage. While it was possible to use the tty devices in the past, the OpenBSD kernel is no longer compatible with this usage.

From [cua\(4\)](#):

For hardware terminal ports, dial-out is supported through matching device nodes called calling units. For instance, the terminal called /dev/tty03 would have a matching calling unit called /dev/cua03. These two devices are normally differentiated by creating the calling unit device node with a minor number 128 greater than the dial-in device node. *Whereas the dial-in device (the tty) normally requires a hardware signal to indicate to the system that it is active, the dial-out device (the cua) does not, and hence can communicate unimpeded with a device such as a modem.* This means that a process like [getty\(8\)](#) will wait on a dial-in device until a connection is established. Meanwhile, a dial-out connection can be established on the dial-out device (for the very same hardware terminal port) without disturbing anything else on the system. The [getty\(8\)](#) process does not even notice that anything is happening on the terminal port. If a connecting call comes in after the dial-out connection has finished, the [getty\(8\)](#) process will deal with it properly, without having noticed the intervening dial-out action.

## 8.14 - What web browsers are available for OpenBSD?

[Lynx](#), a text-based browser, is in the base system, and has SSL support. Other browsers in the ports tree, include (in no particular order):

### Graphical (X) Browsers

- [Dillo](#) Minimal feature set, very fast and small, runs well on slower hardware.
- [Konqueror](#) Installed as part of the [KDE desktop environment](#).
- [Konqueror-embedded](#) (konq-e) Konqueror, using only the KDE libraries rather than all of KDE.
- [Netscape 4](#) For sparc and i386 only, not Open Source, no package available.
- [Opera](#) Commercial browser.
- [Amaya](#) The W3C's browser and editor.
- [Links+](#) Another fast and small graphical browser. (Also has a text-only mode)

### Console (Text mode) Browsers

- [w3m](#) Has table and frame support (also has a graphical mode).
- [links](#) Has table support.

[Mozilla](#) is not supported on OpenBSD 3.3-*release* or -*stable*. Work is progressing on this in -*current*. See the [mailing list](#) archives for details.

You will find all these in the [ports collection](#). All the above mentioned browsers are located in /usr/ports/www/ after the installation of the ports tree. Most are also available as pre-compiled [packages](#), available on the [FTP servers](#) and on the [CD-ROM](#). As most of the graphical browsers are very large and require quite some time to download and compile, one should seriously consider the use of packages where available.

## 8.15 - How do I use the mg editor?

Mg is a micro Emacs-style text editor included in OpenBSD. Micro means that it's small (Emacs is very large!) For the basics, read the [mg\(1\)](#) manual page and the [tutorial](#), as included with the source code. For more interesting questions (such as, "I don't have a Meta key!") check out the [Emacs FAQ](#).

Note that since mg is a small Emacs implementation, which is mostly similar to the text editor features of Emacs 17, it does not implement many of Emacs' other functionality. (Including mail and news functionality, as well as modes for Lisp, C++, Lex, Awk, Java, etc...)

## 8.16 - ksh(1) does not appear to read my .profile!

There are two likely reasons for [ksh\(1\)](#) to seemingly ignore a user's `.profile` file.

- `.profile` is not owned by the user. To fix for `username`,

```
# chown username ~username/.profile
```

- You are using `ksh(1)` from within X Window System

Under [xterm\(1\)](#), `argv[0]` for `ksh(1)` is not prepended with a dash ("-"). Prepending a dash to `argv[0]` will cause `csh(1)` and `ksh(1)` to know they should interpret their login files. (For `csh(1)` that's `.login`, with a separate `.cshrc` that is always run when `csh(1)` starts up. With `ksh(1)`, this is more noticeable because there is only one startup script, `.profile`. This file is ignored unless the shell is a login shell.)

To fix this, add the line "XTerm\*loginShell: true" to the file `.Xdefaults` in your home directory. Note, this file does not exist by default, you may have to create it.

```
$ echo "XTerm*loginShell: true" >> ~/.Xdefaults
```

You may not have had to do this on other systems, as some installations of X Window System come with this setting as default. OpenBSD has chosen to follow the XFree86 behavior.

## 8.17 - Why does my `/etc/motd` file get overwritten when I modified it?

The `/etc/motd` file is edited upon every boot of the system, replacing everything up to, but not including, the first blank line with the system's kernel version information. When editing this file, make sure that you start after this blank line, to keep `/etc/rc` from deleting these lines when it edits `/etc/motd` upon boot.

## 8.18 - Why does [www.openbsd.org](http://www.openbsd.org) run on Solaris?

Although none of the developers think it is particularly relevant, this question comes up frequently enough in the mailing lists that it is answered here. [www.openbsd.org](http://www.openbsd.org) and the main OpenBSD ftp site are hosted at a [SunSITE](http://www.sunsite.ualberta.ca) at the University of Alberta, Canada. These sites are hosted on a large Sun system, which has access to lots of storage space and Internet bandwidth. The presence of the SunSITE gives the OpenBSD group access to this bandwidth. This is why the main site runs here. Many of the OpenBSD mirror sites run OpenBSD, but since they do not have guaranteed access to this large amount of bandwidth, the group has chosen to run the main site at the University of Alberta SunSITE.

## 8.19 - I'm having problems with my PCI devices being detected

There exists a condition where some machines might not detect some PCI devices properly, or might freeze while detecting multiple NIC's in one machine. This is the fault of PCIBIOS, and involves a simple workaround to make it work properly. Simply enter the boot time configuration and disable PCIBIOS. An example is below:

```
boot> boot -c
Copyright (c) 1982, 1986, 1989, 1991, 1993
    The Regents of the University of California. All rights reserved.
Copyright (c) 1995-2002 OpenBSD. All rights reserved. http://www.OpenBSD.org

OpenBSD 3.3 (GENERIC) #44: Sat Mar 29 13:22:05 MST 2003
    deraadt@i386.openbsd.org:/usr/src/sys/arch/i386/compile/RAMDISK_CD
cpu0: Intel Pentium III (Coppermine) ("GenuineIntel" 686-class, 128KB L2 cache)
1 GHz
cpu0: FPU,V86,DE,PSE,TSC,MSR,PAE,MCE,CX8,SYS,MTRR,PGE,MCA,CMOV,PAT,PSE36,MMX,FXS
R,SIMD
real mem = 267956224 (261676K)
avail mem = 243347456 (237644K)
using 3296 buffers containing 13500416 bytes (13184K) of memory
User Kernel Config
UKC> disable pcibios
UKC> quit
[... snip ...]
```

Once this is done, you can follow the directions in [FAQ 5, Building a Kernel](#) to create a new kernel so that you don't have to worry about this in the future.

## 8.20 - Antialiased and TrueType fonts in XFree86

See [this document](#).

## 8.21 - Does OpenBSD support any journaling filesystems?

No it doesn't. We use a different mechanism to achieve similar results that is called [Soft Updates](#). Please read in FAQ 14 to get more details.

## 8.22 - Reverse DNS

- or -

### Why is it taking so long for me to log in?

Many new users to OpenBSD experience a two minute login delay when using services such as [ssh](#), [ftp](#), or [telnet](#). This can also be experienced when using a proxy, such as [ftp-proxy](#), or when sending mail out from a workstation through [sendmail](#).

This is almost always due to a reverse-DNS problem. DNS is Domain Name Services, the system the Internet uses to convert a name, such as "www.openbsd.org" into a numeric IP address. Another task of DNS is the ability to take a numeric address and convert it back to a "name", this is "Reverse DNS".

In order to provide better logging, OpenBSD performs a reverse-DNS lookup on any machine that attaches to it in many different ways, including [ssh](#), [ftp](#), [telnet](#), [sendmail](#) or [ftp-proxy](#). Unfortunately, in some cases, the machine that is making the connection does not have a proper reverse DNS entry.

### An example of this situation:

A user sets up an OpenBSD box as a firewall and gateway to their internal home network, mapping all their internal computers to one external IP using [NAT](#). They may also use it as an outbound mail relay. They follow the installation guidelines, and are very happy with the results, except for one thing -- every time they try to attach to the box in any way, they end up with a two minute delay before things happen.

### What is going on:

From a workstation behind the NAT of the gateway with an [unregistered IP](#) address of 192.168.1.35, the user uses [ssh](#) to access the gateway system. The [ssh](#) client prompts for username and password, and sends them to the gateway box. The gateway then tries to figure out who is trying to log in by performing a reverse DNS lookup of 192.168.1.35. The problem is 192.168.0.0 addresses are for private use, so a properly configured DNS server outside your network knows it should have no information about those addresses. Some will quickly return an error message, in these cases, OpenBSD will assume there is no more information to be gained, and it will quickly give up and just admit the user. Other DNS servers will not return ANY response. In this case you will find yourself waiting for the OpenBSD name resolver to time out, which takes about two minutes before the login will be permitted to continue. In the case of [ftp-proxy](#), some ftp clients will timeout before the reverse DNS query times out, leading to the impression that ftp-proxy isn't working.

This can be quite annoying. Fortunately, it is an easy thing to fix.

### Fix, using `/etc/hosts`:

The simplest fix is to populate your `/etc/hosts` file with all the workstations you have in your internal network, and ensure that your `/etc/resolv.conf` file contains the line `lookup file bind` which ensures that the resolver knows to start with the `/etc/hosts` file, and failing that, to use the DNS servers specified by the "nameserver" lines in your `/etc/resolv.conf` file.

Your `/etc/hosts` file will look something like this:

```
:::1 localhost.in.example.org localhost
127.0.0.1 localhost.in.example.org localhost
192.168.1.1 gw.in.example.org gw
192.168.1.20 scrappy.in.example.org scrappy
192.168.1.35 shadow.in.example.org shadow
```

Your `resolv.conf` file will look something like this:

```
search in.example.org
nameserver 24.2.68.33
nameserver 24.2.68.34
lookup file bind
```

A common objection to this is "But, I use DHCP for my internal network! How can I configure my `/etc/hosts`?" Rather easily, actually. Just enter lines for all the addresses your DHCP server is going to give out, plus any static devices:

```
:::1 localhost.in.example.org localhost
127.0.0.1 localhost.in.example.org localhost
192.168.1.1 gw.in.example.org gw
192.168.1.20 scrappy.in.example.org scrappy
192.168.1.35 shadow.in.example.org shadow
192.168.1.100 d100.in.example.org d100
192.168.1.101 d101.in.example.org d101
192.168.1.102 d102.in.example.org d102
[... snip ...]
192.168.1.198 d198.in.example.org d198
192.168.1.199 d199.in.example.org d199
```

In this case, I am assuming you have the DHCP range set to 192.168.1.100 through 192.168.1.199, plus the three static definitions as listed at the top of the file.

If your gateway must use DHCP for configuration, you may well find you have a problem -- [dhclient](#) will overwrite your `/etc/resolv.conf` every time the lease is renewed, which will remove the "lookup file bind" line. This can be solved by putting the line "lookup file bind" in the file `/etc/resolv.conf.tail`.

## Fix, using a local DNS server

Details on this are somewhat beyond the scope of this document, but the basic trick is to setup your favorite DNS server, and make sure it knows it is authoritative for both forward and reverse DNS resolution for all nodes in your network, and make sure your computers (including your gateway) know to use it as a DNS server.

## 8.23 - Why do the OpenBSD web pages not conform to HTML4/XHTML?

The present web pages have been carefully crafted to work on a wide variety of actual browsers going back to browser versions 4.0 and later. We do not want to make these older pages conform to HTML4 or XHTML until we're sure that they will also work with older browsers; it's just not a priority. We welcome new contributors, but suggest you work on writing code, or on documenting new aspects of the system, not on tweaking the existing web pages to conform to newer standards.

## 8.24 - Why is my clock off by twenty-some seconds?

When using [rdate\(8\)](#) to synchronize your clock to a NTP server, you may find your clock is off by twenty-some seconds from your local definition of time.

This is caused by a difference between the UTC (Coordinated Universal Time, based on astronomical observations) time and TAI (International Atomic Time, based on atomic clocks) time. To compensate for variations in the earth's rotation, "leap seconds" are inserted into UTC, but TAI is unadjusted. These leap seconds are the cause of this discrepancy. For a more detailed description, search the web for "leap seconds UTC TAI".

Addressing the problem is fairly simple. In most countries you will get the correct time if you use the "-c" parameter to [rdate\(8\)](#) and use a time zone out of the directory `/usr/share/zoneinfo/right/`. For example, if you are located in Germany, you could use these commands:

```
# cd /etc && ln -sf /usr/share/zoneinfo/right/CET localtime
# rdate -ncv ptbtime1.ptb.de
```

In other countries, the rules may differ.

[\[FAQ Index\]](#) [\[To Section 7 - Keyboard and Display Controls\]](#) [\[To Section 9 - Migrating from Linux\]](#)



[www@openbsd.org](mailto:www@openbsd.org)

\$OpenBSD: faq8.html,v 1.135 2003/10/16 00:48:13 nick Exp \$



[\[FAQ Index\]](#) [\[To Section 8 - General Questions\]](#) [\[To Section 10 - System Management\]](#)

## 9 - Migrating from Linux

---

### Table of Contents

- [9.1 - Tips for Linux \(and other free Unix-like OS\) users](#)
- [9.2 - Dual boot of Linux and OpenBSD](#)
- [9.3 - Converting your Linux \(or other System-7 style\) password file to BSD-style.](#)
- [9.4 - Getting OpenBSD and Linux to interact](#)

For more information for Linux users, please refer to <http://sites.inka.de/mips/unix/bsdlinux.html>.

---

### 9.1 - Simple tips for Linux (and other free Unix-like OS) users

There are several differences between OpenBSD and Linux. These differences include but are not limited to, bootup procedure, network interface usage and disk management. Most differences are well documented, but involve searching manpages. This document tries to be an index of those differences.

- OpenBSD has a [ports tree](#). This is to accommodate the fact that at this point not many applications are native to the OpenBSD environment. This is both an attempt to get applications to work on OpenBSD for end-users and to get more applications made with OpenBSD in mind. Eventually this ports tree is used to make a nice set of binary [packages](#).
- OpenBSD uses CVS for source changes. With Linux, source code is disseminated through separate distributions. OpenBSD pioneered anonymous CVS, which allows anyone to extract the full source tree for any version of OpenBSD (from 2.0 to current, and all revisions of all files in between) at any time! There is also a very convenient and easy to use [web interface to CVS](#).
- OpenBSD periodically releases snapshots for various architectures and makes a stable, official CD release every 6 months.
- OpenBSD contains STRONG CRYPTO, which USA based OS's can't contain. (See <http://www.openbsd.org/crypto.html>) OpenBSD has also gone through heavy security auditing and many security features have already been implemented into the source tree. (IPSEC, KERBEROS).
- OpenBSD's kernel is /bsd.
- The names of hard disks are usually `/dev/wd` (IDE) and `/dev/sd` (SCSI or ATA devices emulating SCSI disks)
- `/sbin/ifconfig` with no arguments in Linux gives the state of all the interfaces. Under OpenBSD you need the `-a` flag.
- `/sbin/route` with no arguments in Linux gives the state of all the active routes. Under OpenBSD you need the `"show"` parameter, or do a `netstat -r` (nice).
- OpenBSD does NOT support Journaling Filesystems like ReiserFS, IBMs JFS or SGIs XFS. Instead we use [Soft Updates](#).
- OpenBSD comes with Packet Filter (PF), not ipfw, ipchains, netfilter, iptables, or ipf. This means that:
  - Network Address Translation (known as IP-Masquerading in Linux) is done through pfctl (using `-N`). ([pfctl\(8\)](#))
  - ipfwadm is done through pfctl. ([pfctl\(8\)](#), [pf\(4\)](#), [pf.conf\(5\)](#))
  - You should look at [section 6](#) for detailed configuration assistance and information.

- Interface address is stored in `/etc/hostname.<interfacename>`. It can be a hostname instead of an IP address.
- The machine name is in `/etc/myname`
- The default gateway is in `/etc/mygate`
- OpenBSD's default shell is `/bin/sh`, which is the Korn shell. Shells such as `bash` and `tcsh` can be added as packages or installed from the ports tree.
- Password management changes a lot. The main files are different. ([passwd\(1\)](#), [passwd\(5\)](#))
- Devices are named by driver, not by type. For example, there are no `eth*` devices. It would be `ne0` for an ne2000 ethernet card, and `xl0` for a 3Com Etherlink XL and Fast Etherlink XL ethernet device, etc.
- OpenBSD developers have made serious efforts to keep the manual pages up-to-date and accurate. Use the [man\(1\)](#) command to find information.

## 9.2 - Dual booting Linux and OpenBSD

Yes! It is possible!

Read [INSTALL.linux](#).

## 9.3 - Converting your Linux (or other System 7-style) password file to BSD-style

First, figure out if your Linux password file is shadowed or not. If it is, grab [John the Ripper](#) and use the `unshadow` utility that comes with it to merge your `passwd` and `shadow` files into one System 7-style file.

Using your Linux password file, we'll call it `linux_passwd`, you need to add in `::0:0` between fields four and seven. [awk\(1\)](#) does this for you.

```
# cat linux_passwd | awk -F : '{printf("%s:%s:%s:%s::0:0:%s:%s:%s\n", \
> $1,$2,$3,$4,$5,$6,$7); }' > new_passwd
```

At this point, you want to edit the `new_passwd` file and remove the root and other system entries that are already present in your OpenBSD password file or aren't applicable with OpenBSD (all of them). Also, make sure there are no duplicate usernames or user IDs between `new_passwd` and your OpenBSD box's `/etc/passwd`. The easiest way to do this is to start with a fresh `/etc/passwd`.

```
# cat new_passwd >> /etc/master.passwd
# pwd_mkdb -p /etc/master.passwd
```

The last step, `pwd_mkdb` is necessary to rebuild the `/etc/spwd.db` and `/etc/pwd.db` files. It also creates a System 7-style password file (minus encrypted passwords) at `/etc/passwd` for programs which use it. OpenBSD uses a stronger encryption for passwords, blowfish, which is very unlikely to be found on any system which uses full System 7-style password files. To switch over to this stronger encryption, simply have the users run `'passwd'` and change their password. The new password they enter will be encrypted with your default setting (usually blowfish unless you've edited `/etc/login.conf`). Or, as root, you can run `passwd username`.

## 9.4 - Getting OpenBSD and Linux to interact

If you are migrating from Linux to OpenBSD, note that OpenBSD has `COMPAT_LINUX` enabled by default in the `GENERIC` kernel. To run any Linux binaries that are not statically linked (most of them), you need to follow the instructions on the

[compat\\_linux\(8\)](#) manual page. A simple way to get most of the useful Linux libraries is to install the `redhat/base` port from your ports collection. To find out more about the Ports collection read [FAQ 8 - Ports](#). If you already have the ports tree installed, use these commands to get Linux libraries installed.

```
# cd /usr/ports/emulators/redhat/base
# make install
```

OpenBSD supports the EXT2FS file system. Use [disklabel \(8\)](#) *disk* (where *disk* is the device name for your disk.) to see what OpenBSD thinks your Linux partition is (but **don't** use `disklabel` or `fdisk` to make any changes to it). For further information on using `disklabel` read [FAQ 14 - Disklabel](#).

[\[FAQ Index\]](#) [\[To Section 8 - General Questions\]](#) [\[To Section 10 - System Management\]](#)



[www@openbsd.org](mailto:www@openbsd.org)

\$OpenBSD: faq9.html,v 1.55 2003/10/26 02:05:59 nick Exp \$

# OpenBSD

[\[FAQ Index\]](#) [\[To Section 9 - Migrating from Linux\]](#) [\[To Section 11 - Performance Tuning\]](#)

## 10 - System Management

---

### Table of Contents

- [10.1 - When I try to su to root it says that I'm in the wrong group.](#)
  - [10.2 - How do I duplicate a filesystem?](#)
  - [10.3 - How do I start daemons with the system? \(Overview of rc\(8\)\)](#)
  - [10.4 - Why do users get relaying access denied when they are remotely sending mail through my OpenBSD system?](#)
  - [10.5 - I've set up POP, but I get errors when accessing my mail through POP. What can I do?](#)
  - [10.6 - Why does Sendmail ignore /etc/hosts?](#)
  - [10.7 - Setting up a Secure HTTP Server using ssl\(8\)](#)
  - [10.8 - I made changes to /etc/passwd with an editor, but the changes didn't seem to take place. Why?](#)
  - [10.9 - How do I add a user? Or delete a user?](#)
  - [10.10 - How do I create a ftp-only account?](#)
  - [10.11 - Setting up user disk quotas](#)
  - [10.12 - Setting up KerberosV Clients and Servers](#)
  - [10.13 - Setting up an Anonymous FTP Server](#)
  - [10.14 - Confining users to their home directories in ftpd\(8\)](#)
  - [10.15 - Applying patches in OpenBSD](#)
  - [10.16 - Tell me about chroot\(\) Apache?](#)
  - [10.17 - I don't like the standard root shell!](#)
  - [10.18 - What else can I do with ksh?](#)
- 

### 10.1 - Why does it say that I'm in the wrong group when I try to su root?

Existing users must be added to the "wheel" group by hand. This is done for security reasons, and you should be cautious with whom you give access to. On OpenBSD, users who are in the wheel group are allowed to use the [su\(1\)](#) userland program to become root. Users who are not in "wheel" cannot use su(1). Here is an example of a /etc/group entry to place the user **ericj** into the "wheel" group.

If you are adding a new user with [adduser\(8\)](#), you can put them in the wheel group by answering wheel at "Invite user into other groups:". This will add them to /etc/group, which will look something like this:

```
wheel:*:0:root,ericj
```

If you are looking for a way to allow users limited access to superuser privileges without putting them in the "wheel" group, use [sudo\(8\)](#).

### 10.2 - How do I duplicate a filesystem?

To duplicate your filesystem use [dump\(8\)](#) and [restore\(8\)](#). For example, to duplicate everything under directory SRC to directory DST, do a:

```
# cd /SRC; dump 0f - . | (cd /DST; restore -rf - )
```

dump is designed to give you plenty of backup capabilities, and it may be an overkill if you just want to duplicate a part of a (or an entire) filesystem. The command [tar\(1\)](#) may be faster for this operation. The format looks very similar:

```
# cd /SRC; tar cf - . | (cd /DST; tar xpf - )
```

## 10.3 - How do I start daemons with the system? (Overview of rc(8))

OpenBSD uses an [rc\(8\)](#) style startup. This uses a few key files for startup.

- `/etc/rc` - Main script. Should not be edited.
- `/etc/rc.conf` - Configuration file used by `/etc/rc` to know what daemons should start with the system.
- `/etc/rc.conf.local` - Configuration file you can use to override settings in `/etc/rc.conf` so you don't have to touch `/etc/rc.conf` itself, which is convenient for people who upgrade often.
- `/etc/netstart` - Script used to initialize the network. Shouldn't be edited.
- `/etc/rc.local` - Script used for local administration. This is where new daemons or host specific information should be stored.
- `/etc/rc.securelevel` - Script which runs commands that must be run before the security level changes. See [init\(8\)](#)
- `/etc/rc.shutdown` - Script run on shutdown. Put anything you want done before shutdown in this file. See [rc.shutdown\(8\)](#)

### How does rc(8) work?

The main files a system administrator should concentrate on are `/etc/rc.conf` (or `/etc/rc.conf.local`), `/etc/rc.local` and `/etc/rc.shutdown`. To get a look of how the rc(8) procedure works, here is the flow:

After the kernel is booted, `/etc/rc` is started:

- Filesystems are checked. This will be bypassed if the file `/etc/fastboot` exists. This is certainly not a good idea though.
- Configuration variables are read in from `/etc/rc.conf` and, afterwards, `/etc/rc.conf.local`. Settings in `rc.conf.local` will override those in `rc.conf`.
- Filesystems are mounted
- Clears out `/tmp` and preserves any editor files
- Configures the network via `/etc/netstart`
  - Configures your interfaces up.
  - Sets your hostname, domainname, etc.
- Starts system daemons
- Performs various other checks (quotas, savecore, etc)
- Local daemons are run, via `/etc/rc.local`

### Starting Daemons and Services that come with OpenBSD

Most daemons and services that come with OpenBSD by default can be started on boot by simply editing the `/etc/rc.conf` configuration file. To start out take a look at the default [/etc/rc.conf](#) file. You'll see lines similar to this:

```
ftpd_flags=NO           # for non-inetd use: ftpd_flags="-D"
```

A line like this shows that ftpd is not to start up with the system (at least not via rc(8), read the [Anonymous FTP FAQ](#) to read more about this). In any case, each line has a comment showing you the flags for **NORMAL** usage of that daemon or service. This doesn't mean that

you must run that daemon or service with those flags. You can always use `man(1)` to see how you can have that daemon or service start up in any way you like. For example, here is the default line pertaining to `httpd(8)`.

```
httpd_flags=NO          # for normal use: "" (or "-DSSL" after reading ssl(8))
```

Here you can obviously see that starting up `httpd` normally no flags are necessary. So a line like: "`httpd_flags=""`" would be necessary. But to start `httpd` with `ssl` enabled. (Refer to the [SSL FAQ](#) or [ssl\(8\)](#)) You should start with a line like: "`httpd_flags="-DSSL"`".

A good approach is to never touch `/etc/rc.conf` itself. Instead, create the file `/etc/rc.conf.local`, copy just the lines you are about to change from `/etc/rc.conf` and adjust them as you like. This may make future upgrading easier -- all the changes are in the one file.

## Starting up local daemons and configuration

For other daemons that you might install with the system via ports or other ways, you should use the `/etc/rc.local` file. For example, I've installed a daemon which lies at `/usr/local/sbin/daemonx`. I want this to start at boot time. I would put an entry into `/etc/rc.local` like this:

```
if [ -x /usr/local/sbin/daemonx ]; then
    echo -n ' daemonx';          /usr/local/sbin/daemonx
fi
```

(If the daemon does not automatically detach on startup, remember to add a "&" at the end of the command line.)

From now on, this daemon will be run at boot. You will be able to see any errors on boot, a normal boot with no errors would show a line like this:

```
Starting local daemons: daemonx.
```

## rc.shutdown

`/etc/rc.shutdown` is a script that is run at shutdown. Anything you want done before the system shuts down should be added to this file. If you have `apm`, you can also set "`powerdown=YES`". Which will give you the equivalent of "`shutdown -p`".

## 10.4 - Why do users get "relaying denied" when they are remotely sending mail through my OpenBSD system?

Try this:

```
# cat /etc/mail/sendmail.cf | grep relay-domains
```

The output may look something like this:

```
FR-o /etc/mail/relay-domains
```

If this file doesn't exist, create it. You will need to enter the hosts who are sending mail remotely with the following syntax:

```
.domain.com    #Allow relaying for/to any host in domain.com
sub.domain.com #Allow relaying for/to sub.domain.com and any host in that domain
10.2           #Allow relaying from all hosts in the IP net 10.2.*.*
```

Don't forget send a 'HangUP' signal to `sendmail`, (a signal which causes most daemons to re-read their configuration file):

```
# kill -HUP `head -1 /var/run/sendmail.pid`
```

## Further Reading

- <http://www.sendmail.org/~ca/email/relayingdenied.html>
- <http://www.sendmail.org/tips/relaying.html>
- <http://www.sendmail.org/antispam.html>

## 10.5 - I've set up POP, but users have trouble accessing mail through POP. What can I do?

Most issues dealing with POP are problems with temporary files and lock files. If your pop server sends an error message such as:

```
-ERR Couldn't open temporary file, do you own it?
```

Try setting up your permissions as such:

```
permission in /var
drwxrwxr-x  2 bin      mail      512 May 26 20:08 mail

permissions in /var/mail
-rw-----  1 username  username  0 May 26 20:08 username
```

Another thing to check is that the user actually owns their own `/var/mail` file. Of course this should be the case (as in, `/var/mail/joe` should be owned by joe) but if it isn't set correctly it could be the problem!

Of course, making `/var/mail` writable by group mail opens up some vague and obscure security problems. It is likely that you will never have problems with it. But it could (especially if you are a high profile site, ISP,...)! There are several POP servers you can install right away from the ports collection. If possible, use [popa3d](#) which is available in the OpenBSD base install. Or, you could just have the wrong options selected for your pop daemon (like dot locking). Or, you may just need to change the directory that it locks in (although then the locking would only be valuable for the POP daemon.)

**PS:** Notice, OpenBSD does not have a group name of "mail". You need to create this in your `/etc/group` file if you need it. An entry like:

```
mail:*:6:
```

would be sufficient.

## 10.6 - Why does Sendmail ignore `/etc/hosts` file?

By default, Sendmail uses DNS for name resolution, not the `/etc/hosts` file. The behavior can be changed through the use of the `/etc/mail/service.switch` file.

If you wish to query the hosts file before DNS servers, create a `/etc/mail/service.switch` file which contains the following line:

```
hosts      files dns
```

If you wish to query ONLY the hosts file, use the following:

```
hosts      files
```

Send Sendmail a HUP signal:

```
# kill -HUP `head -1 /var/run/sendmail.pid`
```

and the changes will take effect.

## 10.7 - Setting up a Secure HTTP server with SSL(8)

OpenBSD ships with an SSL-ready `httpd` and RSA libraries. For use with [httpd\(8\)](#), you must first have a certificate created. This will be kept in `/etc/ssl/` with the corresponding key in `/etc/ssl/private/`. The steps shown here are taken in part from the [ssl\(8\)](#) man page. Refer to it for further information. This FAQ entry only outlines how to create an RSA certificate for web servers, not a DSA server certificate. To find out how to do so, please refer to the [ssl\(8\)](#) man page.

To start off, you need to create your server key and certificate using OpenSSL:

```
# openssl genrsa -out /etc/ssl/private/server.key 1024
```

Or, if you wish the key to be encrypted with a passphrase that you will have to type in when starting servers

```
# openssl genrsa -des3 -out /etc/ssl/private/server.key 1024
```

The next step is to generate a Certificate Signing Request which is used to get a Certifying Authority (CA) to sign your certificate. To do this use the command:

```
# openssl req -new -key /etc/ssl/private/server.key -out /etc/ssl/private/server.csr
```

This `server.csr` file can then be given to Certifying Authority who will sign the key. One such CA is **Thawte Certification** which you can reach at <http://www.thawte.com/>.

If you cannot afford this, or just want to sign the certificate yourself, you can use the following.

```
# openssl x509 -req -days 365 -in /etc/ssl/private/server.csr \
  -signkey /etc/ssl/private/server.key -out /etc/ssl/server.crt
```

With `/etc/ssl/server.crt` and `/etc/ssl/private/server.key` in place, you should be able to start [httpd\(8\)](#) with the `-DSSL` flag (see the [section about rc\(8\)](#) in this faq), enabling https transactions with your machine on port 443.

## 10.8 - I edited /etc/passwd, but the changes didn't seem to take place. Why?

If you edit `/etc/passwd` directly, your changes will be lost. OpenBSD generates `/etc/passwd` dynamically with [pwd\\_mkdb\(8\)](#). The main password file in OpenBSD is `/etc/master.passwd`. According to [pwd\\_mkdb\(8\)](#),

```
FILES
  /etc/master.passwd  current password file
  /etc/passwd         a Version 7 format password file
  /etc/pwd.db         insecure password database file
```

```

/etc/pwd.db.tmp      temporary file
/etc/spwd.db        secure password database file
/etc/spwd.db.tmp    temporary file

```

In a traditional Unix password file, such as `/etc/passwd`, everything including the user's encrypted password is available to anyone on the system (and is a prime target for programs such as Crack). 4.4BSD introduced the `master.passwd` file, which has an extended format (with additional options beyond those provided by `/etc/passwd`) and is only readable by root. For faster access to data, the library calls which access this data normally read `/etc/pwd.db` and `/etc/spwd.db`.

OpenBSD does come with a tool with which you should edit your password file. It is called `vipw(8)`. `Vipw` will use `vi` (or your favourite editor defined per `$EDITOR`) to edit `/etc/master.passwd`. After you are done editing, it will re-create `/etc/passwd`, `/etc/pwd.db`, and `/etc/spwd.db` as per your changes. `Vipw` also takes care of locking these files, so that if anyone else attempts to change them at the same time, they will be denied access.

## 10.9 - What is the best way to add and delete users?

OpenBSD provides two commands for easily adding users to the system:

- [adduser\(8\)](#)
- [user\(8\)](#)

You can also add users by hand, using [vipw\(8\)](#), but this is more difficult for most operations.

The easiest way to add a user in OpenBSD is to use the [adduser\(8\)](#) script. You can configure `adduser(8)` by editing `/etc/adduser.conf`. `adduser(8)` allows for consistency checks on `/etc/passwd`, `/etc/group`, and shell databases. It will create the entries and `$HOME` directories for you. It can even send a message to the user welcoming them. Here is an example user, **testuser**, being added to a system. He/she will be given the `$HOME` directory `/home/testuser`, made a member of the group **guest**, and given the shell `/bin/ksh`.

```

# adduser
Use option ``-silent'' if you don't want to see all warnings and questions.

Reading /etc/shells
Reading /etc/login.conf
Check /etc/master.passwd
Check /etc/group

Ok, let's go.
Don't worry about mistakes. I will give you the chance later to correct any input.
Enter username []: testuser
Enter full name []: Test FAQ User
Enter shell csh ksh nologin sh [sh]: ksh
Uid [1002]: Enter
Login group testuser [testuser]: guest
Login group is ``guest''. Invite testuser into other groups: guest no
[no]: no
Login class auth-defaults auth-ftp-defaults daemon default staff
[default]: Enter
Enter password []: Type password, then Enter
Enter password again []: Type password, then Enter

Name:      testuser
Password:  ****
Fullname:  Test FAQ User
Uid:      1002
Gid:      31 (guest)
Groups:    guest
Login Class: default
HOME:     /home/testuser

```

```
Shell:i      /bin/ksh
OK? (y/n) [y]: y
Added user ``testuser''
Copy files from /etc/skel to /home/testuser
Add another user? (y/n) [y]: n
Goodbye!
```

To delete users you should use the [rmuser\(8\)](#) utility. This will remove all existence of a user. It will remove any [crontab\(1\)](#) entries, their \$HOME dir (if it is owned by the user), and their mail. Of course it will also remove their */etc/passwd* and */etc/group* entries. Next is an example of removing the user that was added above. Notice you are prompted for the name, and whether or not to remove the users home directory.

```
# rmuser
Enter login name for user to remove: testuser
Matching password entry:

testuser:$2a$07$ZWnB0sbqMJ.ducQBfsTKUe3PL97Ve1AHWJ0A4uLamniLNXLLeYrEie:1002
:31::0:0:Test FAQ User:/home/testuser:/bin/ksh

Is this the entry you wish to remove? y
Remove user's home directory (/home/testuser)? y
Updating password file, updating databases, done.
Updating group file: done.
Removing user's home directory (/home/testuser): done.
```

## Adding users via user(8)

These tools are less interactive than the [adduser\(8\)](#) command, which makes them easier to use in scripts.

The full set of tools is:

- [group\(8\)](#)
- [groupadd\(8\)](#)
- [groupdel\(8\)](#)
- [groupinfo\(8\)](#)
- [groupmod\(8\)](#)
- [user\(8\)](#)
- [useradd\(8\)](#)
- [userdel\(8\)](#)
- [userinfo\(8\)](#)
- [usermod\(8\)](#)

## Actually adding users

Being that [user\(8\)](#) is not interactive, the easiest way to add users efficiently is to use the [adduser\(8\)](#) command. The actual command */usr/sbin/user* is just a frontend to the rest of the */usr/sbin/user\** commands. Therefore, the following commands can be added by using **user add** or **useradd**, its your choice as to what you want, and doesn't change the use of the commands at all.

In this example, we are adding the same user with the same specifications as the user that was added [above](#). [useradd\(8\)](#) is much easier to use if you know the default setting before adding a user. These settings are located in */etc/usermgmt.conf* and can be viewed by doing so:

```
$ user add -D
group          users
base_dir      /home
skel_dir      /etc/skel
```

```

shell          /bin/csh
inactive      0
expire        Null (unset)
range         1000..60000

```

The above settings are what will be set unless you specify different with command line options. For example, in our case, we want the user to go to the group **guest**, not **users**. One more little hurdle with adding users, is that passwords must be specified on the commandline. This is, the encrypted passwords, so you must first use the [encrypt\(1\)](#) utility to create the password. For example:

OpenBSD's passwords by default use the Blowfish algorithm for 6 rounds. Here is an example line to create an encrypted password to specify to `useradd(8)`.

```

$ encrypt -p -b 6
Enter string:
$2a$06$Y0dOZM3.4m6MObBXjeZtBOWArqC2.uRJZXUkOghbieIvSWXVJRz1q

```

Now that we have our encrypted password, we are ready to add the user.

```

# user add -p '$2a$06$Y0dOZM3.4m6MObBXjeZtBOWArqC2.uRJZXUkOghbieIvSWXVJRz1q' -u 1002 \
-s /bin/ksh -c "Test FAQ User" -m -g guest testuser

```

**Note:** Make sure to use `'` (single quotes) around the password string, not `"` (double quotes) as the shell will interpret these before sending it to `user(8)`. In addition to that, make sure you specify the `-m` option if you want the user's home directory created and the files from `/etc/skel` copied over.

To see that the user was created correctly, we can use many different utilities. Below are a few commands you can use to quickly check that everything was created correctly.

```

$ ls -la /home
total 14
drwxr-xr-x  5 root      wheel   512 May 12 14:29 .
drwxr-xr-x 15 root      wheel   512 Apr 25 20:52 ..
drwxr-xr-x 24 ericj     wheel  2560 May 12 13:38 ericj
drwxr-xr-x  2 testuser  guest   512 May 12 14:28 testuser
$ id testuser
uid=1002(testuser) gid=31(guest) groups=31(guest)
$ finger testuser
Login: testuser                Name: Test FAQ User
Directory: /home/testuser      Shell: /bin/ksh
Last login Sat Apr 22 16:05 (EDT) on ttyC2
No Mail.
No Plan.

```

In addition to these commands, `user(8)` provides its own utility to show user characteristics, called `userinfo(8)`.

```

$ userinfo testuser
login  testuser
passwd *
uid    1002
groups guest
change Wed Dec 31 19:00:00 1969
class
gecos  Test FAQ User
dir    /home/testuser
shell  /bin/ksh
expire Wed Dec 31 19:00:00 1969

```

## Removing users

To remove users with the user(8) hierarchy of commands, you will use userdel(8). This is a very simple, yet usable command. To remove the user created in the last example, simply:

```
# userdel -r testuser
```

Notice the **-r** option, which must be specified if you want the users home directory to be deleted as well. Alternatively, you can specify **-p** and not **-r** and this will lock the user's account, but not remove any information.

## 10.10 - How do I create an ftp-only account (not anonymous FTP!)?

There are a few ways to do this, but a very common way to do such is to add `/usr/bin/false` into `/etc/shells`. Then when you set a users shell to `/usr/bin/false`, they will not be able log in interactively, but will be able to use ftp capabilities. [adduser\(8\)](#) will give them a home dir by default of `/home/<user>`. If this is what you desire it doesn't need to be changed, however you can set this to whatever directory you wish. You can force this user to only be able to see files in their home directory by adding their username to `/etc/ftpchroot`. Using the **-A** option to [ftpd\(8\)](#), you can allow only ftpchroot logins!

## 10.11 - Setting up Quotas

Quotas are used to limit user's space that they have available to them on your disk drives. It can be very helpful in situations where you have limited resources. Quotas can be set by user and/or by group.

The first step to setting up quotas is to make sure that "option QUOTA" is in your [Kernel Configuration](#). This option is in the GENERIC kernel. After this, you need to mark in `/etc/fstab` the filesystems which will have quotas enabled. The keywords `userquota` and `groupquota` should be used to mark each filesystem that you will be using quotas on. By default, the files `quota.user` and `quota.group` will be created at the root of that filesystem to hold the quota information. This default can be overridden by specifying the file name with the quota option in `/etc/fstab`, such as "userquota=`/var/quotas/quota.user`". Here is an example `/etc/fstab` that has one filesystem with userquotas enabled, and the quota file in a non-standard location:

```
/dev/wd0a / ffs rw,userquota=/var/quotas/quota.user 1 1
```

Now it's time to set the user's quotas. To do so you use the utility [edquota\(8\)](#). A simple use is just "edquota `<user>`". `edquota(8)` will use `vi(1)` to edit the quotas unless the environmental variable `EDITOR` is set to a different editor. For example:

```
# edquota ericj
```

This will give you output similar to this:

```
Quotas for user ericj:
/: blocks in use: 62, limits (soft = 0, hard = 0)
   inodes in use: 25, limits (soft = 0, hard = 0)
```

To add limits, edit it to give results like this:

```
Quotas for user ericj:
/: blocks in use: 62, limits (soft = 1000, hard = 1050)
   inodes in use: 25, limits (soft = 0, hard = 0)
```

Note that the quota allocation is in 1k blocks. In this case, the softlimit is set to 1000k, and the hardlimit is set to 1050k. A softlimit is a limit where the user is just warned when they cross it and have until their grace period is up to get their disk usage below their limit. Grace periods can be set by using the **-t** option on `edquota(8)`. After the grace period is over the softlimit is handled as a hardlimit. This usually results in an allocation failure.

Now that the quotas are set, you need to turn the quotas on. To do this use [quotaon\(8\)](#). For example:

```
# quotaon -a
```

This will go through `/etc/fstab` to turn on the filesystems with quota options. Now that quotas are up and running, you can view them using [quota\(1\)](#). Using a command of `"quota <user>"` will give that user's information. When called with no arguments, the `quota(1)` command will give your quota statistics. For example:

```
# quota ericj
```

Will result in output similar to this:

```
Disk quotas for user ericj (uid 1001):
  Filesystem  blocks  quota  limit  grace  files  quota  limit  grace
      /           62   1000   1050         27     0     0
```

By default quotas set in `/etc/fstab` will be started on boot. To turn them off use

```
# quotaoff -a
```

## 10.12 - Setting up KerberosV Clients and Servers

OpenBSD includes KerberosV as a pre-installed component of the default system.

For more information on KerberosV, from your OpenBSD system, use the command:

```
# info heimdal
```

## 10.13 - Setting up Anonymous FTP Services

Anonymous FTP allows users without accounts to access files on your computer via the File Transfer Protocol. This will give an overview of setting up the anonymous FTP server, and its logging, etc.

### Adding the FTP account

To start off, you need to have an account on your system of "ftp". This account shouldn't have a usable password. Here we will set the login directory to `/home/ftp`, but you can put it wherever you want. When using anonymous ftp, the ftp daemon will chroot itself to the home directory of the 'ftp' user. To read up more on that, read the [ftp\(8\)](#) and [chroot\(2\)](#) man pages. Here is an example of adding the ftp user. I will do this using [adduser\(8\)](#). We also need to add `/usr/bin/false` to our `/etc/shells`, this is the "shell" that we will be giving to the ftp user. This won't allow them to login, even though we will give them an empty password. To do this you can simply `echo /usr/bin/false >> /etc/shells`. Also if you wish for that shell to show up during the adduser questions, you need to modify `/etc/adduser.conf`.

```
# adduser
Use option ``-silent'' if you don't want to see all warnings and questions.

Reading /etc/shells
Reading /etc/login.conf
Check /etc/master.passwd
Check /etc/group

Ok, let's go.
```

Don't worry about mistakes. I will give you the chance later to correct any input.

```
Enter username []: ftp
Enter full name []: anonymous ftp
Enter shell csh false ksh nologin sh tcsh zsh [sh]: false
Uid [1002]: Enter
Login group ftp [ftp]: Enter
Login group is ``ftp''. Invite ftp into other groups: guest no
[no]: no
Login class auth-defaults auth-ftp-defaults daemon default staff
[default]: Enter
Enter password []: Enter
Set the password so that user cannot logon? (y/n) [n]: y
```

```
Name:      ftp
Password:  ****
Fullname:  anonymous ftp
Uid:      1002
Gid:      1002 (ftp)
Groups:    ftp
Login Class: default
HOME:     /home/ftp
Shell:    /usr/bin/false
OK? (y/n) [y]: y
Added user ``ftp''
Copy files from /etc/skel to /home/ftp
Add another user? (y/n) [y]: n
Goodbye!
```

## Directory Setup

Along with the user, this created the directory `/home/ftp`. This is what we want, but there are some changes that we will have to make to get it ready for anonymous ftp. Again these changes are explained in the [ftp\(8\)](#) man page.

You **do not** need to make a `/home/ftp/usr` or `/home/ftp/bin` directory.

- `/home/ftp` - This is the main directory. It should be owned by root and have permissions of 555.
- `/home/ftp/etc` - This is entirely optional and not recommended, as it only serves to give out information on users which exist on your box. If you want your anonymous ftp directory to appear to have real users attached to your files, you should copy `/etc/pwd.db` and `/etc/group` to this directory. This directory should be mode 511, and the two files should be mode 444. These are used to give owner names as opposed to numbers. There are no passwords stored in `pwd.db`, they are all in `spwd.db`, so don't copy that over.
- `/home/ftp/pub` - This is a standard directory to place files in which you wish to share. This directory should also be mode 555.

Note that all these directories should be owned by "root". Here is a listing of what the directories should look like after their creation.

```
# pwd
/home
# ls -laR ftp
total 5
dr-xr-xr-x  5 root  ftp    512 Jul  6 11:33 .
drwxr-xr-x  7 root  wheel  512 Jul  6 10:58 ..
dr-x--x--x  2 root  ftp    512 Jul  6 11:34 etc
dr-xr-xr-x  2 root  ftp    512 Jul  6 11:33 pub

ftp/etc:
total 43
dr-x--x--x  2 root  ftp    512 Jul  6 11:34 .
dr-xr-xr-x  5 root  ftp    512 Jul  6 11:33 ..
-r--r--r--  1 root  ftp    316 Jul  6 11:34 group
-r--r--r--  1 root  ftp   40960 Jul  6 11:34 pwd.db
```

```
ftp/pub:
total 2
dr-xr-xr-x  2 root  ftp  512 Jul  6 11:33 .
dr-xr-xr-x  5 root  ftp  512 Jul  6 11:33 ..
```

## Starting up the server and logging

With `ftpd` you can choose to either run it from `inetd` or the `rc` scripts can kick it off. These examples will show our daemon being started from [inetd.conf](#). First we must become familiar with some of the options to `ftpd`. The default line from `/etc/inetd.conf` is:

```
ftp          stream  tcp      nowait  root    /usr/libexec/ftpd      ftpd -US
```

Here `ftpd` is invoked with `-US`. This will log anonymous connections to `/var/log/ftpd` and concurrent sessions to `/var/run/utmp`. That will allow for these sessions to be seen via `who(1)`. For some, you might want to run only an anonymous server, and disallow `ftp` for users. To do so you should invoke `ftpd` with the `-A` option. Here is a line that starts `ftpd` up for anonymous connections only. It also uses `-ll` which logs each connection to `syslog`, along with the `get`, `retrieve`, etc. `ftp` commands.

```
ftp          stream  tcp      nowait  root    /usr/libexec/tcpd      ftpd -llUSA
```

Note - For people using HIGH traffic `ftp` servers, you might want to not invoke `ftpd` from `inetd.conf`. The best option is to comment the `ftpd` line from `inetd.conf` and start `ftpd` from `rc.conf` along with the `-D` option. This will start `ftpd` as a daemon, and has much less overhead as starting it from `inetd`. Here is an example line to start it from `rc.conf`.

```
ftpd_flags="-DllUSA"          # for non-inetd use: ftpd_flags="-D"
```

This of course only works if you have `ftpd` taken out of `/etc/inetd.conf` and made `inetd` re-read its configuration file.

## Other relevant files

- `/etc/ftpwelcome` - This holds the Welcome message for people once they have connected to your `ftp` server.
- `/etc/motd` - This holds the message for people once they have successfully logged into your `ftp` server.
- `.message` - This file can be placed in any directory. It will be shown once a user enters that directory.

## 10.14 - Confining users to their home dir's in ftpd(8)

OpenBSD's [ftpd\(8\)](#) is setup by default to be able to handle this very easily. This is accomplished via the file `/etc/ftpchroot`. Since users cannot always be trusted, it might be necessary to restrain them to their home directories. This behavior is NOT on by default. Here is an example of what the default behavior is like.

```
$ ftp localhost
Connected to localhost.
220 oshibana FTP server (Version 6.4/OpenBSD) ready.
Name (localhost:ericj): ericj
331 Password required for ericj.
Password: *****
230- OpenBSD 3.3 (GENERIC) #44: Sat Mar 29 13:22:05 MST 2003
230-
230- Welcome to OpenBSD: The proactively secure Unix-like operating system.
230-
230- Please use the sendbug(1) utility to report bugs in the system.
230- Before reporting a bug, please try to reproduce it with the latest
230- version of the code. With bug reports, please try to ensure that
230- enough information to reproduce the problem is enclosed, and if a
```

```

230- known fix for it exists, include that as well.
230-
230 User ericj logged in.
Remote system type is UNIX.
Using binary mode to transfer files.
ftp> cd /
250 CWD command successful.
ftp> ls
227 Entering Passive Mode (127,0,0,1,60,7)
150 Opening ASCII mode data connection for 'file list'.
altroot
bin
dev
etc
home
mnt
root
sbin
stand
tmp
usr
var
bsd
sys
boot
226 Transfer complete.
ftp> quit
221 Goodbye.

```

As you can see here, access is granted to the whole server. In a perfect world this is ok, where all users can be trusted, but this isn't so. To limit a user, simply add their name to the file `/etc/ftpchroot`. Here is an example showing user "ericj" being restricted.

```

$ cat /etc/ftpchroot
#      $ OpenBSD: ftpchroot,v 1.3 1996/07/18 12:12:47 deraadt Exp $
#
# list of users (one per line) given ftp access to a chrooted area.
# read by ftpd(8).
ericj

```

This is enough to keep the user "ericj" from escaping from his own directory. As you can see in the next example. The `/` directory has suddenly changed to his home dir!

```

$ ftp localhost
Connected to localhost.
220 oshibana FTP server (Version 6.4/OpenBSD) ready.
Name (localhost:ericj): ericj
331 Password required for ericj.
Password: *****
230 User ericj logged in.
Remote system type is UNIX.
Using binary mode to transfer files.
ftp> cd /
250 CWD command successful.
ftp> ls
227 Entering Passive Mode (127,0,0,1,92,171)
150 Opening ASCII mode data connection for 'file list'.
.login
.mailrc
.profile
.rhosts
.ssh

```

```
.cshrc
work
mail
src
226 Transfer complete.
ftp> quit
221 Goodbye.
```

## 10.15 - Applying patches in OpenBSD

The OpenBSD source tree is constantly changing and improving, along with this fixes to common problems are often made and patches released to the public. These patches appear on the errata web page located at <http://www.openbsd.org/errata.html>, and are separated into categories. These categories correspond to patches that should be applied to different architectures or architecture independent patches.

Note, however, that patches aren't made for new additions to OpenBSD, and are only done for important reliability fixes or security problems that should be addressed right away, although the choice to do so is, as always, up to the administrator.

For the examples I will be patching [talkd\(8\)](#) with a security fix from the patch obtained from [errata.html](#).

### How are these patches different from what I would find in the CVS tree?

All patches posted at <http://www.openbsd.org/errata.html> are patches directly against the latest release's source tree. Patches against the latest CVS tree might also include other changes that wouldn't be wanted on a release system.

### Getting your system ready to be patched.

Patches for the OpenBSD Operating System are distributed as diffs, which are text files that hold differences to the original source code. They are **NOT** distributed in binary form. This means that to patch your system you must have the source code from the **RELEASE** version of OpenBSD readily available. This does not mean that you must have ALL source code to the OpenBSD operating system to patch your system, but must have all code for the program which you are patching. For instance, if you are patching the kernel you must have all source for the kernel on hand.

[cvs\(1\)](#) is a very handy tool that can be used to grab only the source that you need via any of the anonymous cvs servers located around the world. You can get a listing of these servers at <http://www.openbsd.org/anoncv.html>.

To retrieve the source code for talkd(8) from 3.3-release using [cvs\(1\)](#), you would use the following lines:

```
$ export CVSROOT=anoncv@anoncv5.usa.openbsd.org:/cvs
$ cvs co -rOPENBSD_3_3_BASE src/libexec/talkd/
cvs server: Updating src/libexec/talkd
U src/libexec/talkd/announce.c
U src/libexec/talkd/talkd.c
U src/libexec/talkd/talkd.h
```

To find the CVS path to the code that you need, you can find this in the patch on the *Index:* line. In this case, the CVS path was *src/libexec/talkd/*. Always check out the revision of OPENBSD\_version\_number\_BASE. Without "\_BASE" you will be checking out the stable branch, which might contain other changes that will interfere. If you are already tracking the patch branch, the patches should already be in that source, however you should always check and make sure. You can always look at <http://www.openbsd.org/plus.html> to see which patches have been applied to the patch branch. If the patches haven't been applied yet, you will need to grab the latest release source using the commands above.

Also, for those users that bought official OpenBSD CDs, you can get the source code directly off of the CD. Refer to the CD insert on how to extract the source from the CD. In which case you won't need to obtain the source via anoncv.

```
Apply by doing:
    cd /usr/src
    patch -p0 < 026_talkd.patch
    cd libexec/talkd
    make obj && make depend && make && make install
```

```
Index: libexec/talkd/announce.c <----- Path to sources
=====
RCS file: /cvs/src/libexec/talkd/announce.c,v
retrieving revision 1.8
retrieving revision 1.9
diff -u -r1.8 -r1.9
--- libexec/talkd/announce.c    1998/08/18 03:42:10    1.8
+++ libexec/talkd/announce.c    2000/07/06 00:01:45    1.9
@@ -160,6 +160,6 @@
         *(bptr++) = '\n';
     }
     *bptr = '\0';
-    fprintf(tf, big_buf);
+    fprintf(tf, "%s", big_buf);
     fflush(tf);
 }
```

Once you've obtained the proper sources, you can obtain the patch and place it in *src/*

## Applying Patches

```
$ cd /usr/src
$ patch -p0</path/to/026_talkd.patch
Hmm... Looks like a unified diff to me...
The text leading up to this was:
-----
|Apply by doing:
|    cd /usr/src
|    patch -p0 < 026_talkd.patch
|    cd libexec/talkd
|    make obj && make depend && make && make install
|
|Index: libexec/talkd/announce.c
|=====
|RCS file: /cvs/src/libexec/talkd/announce.c,v
|retrieving revision 1.8
|retrieving revision 1.9
|diff -u -r1.8 -r1.9
|--- libexec/talkd/announce.c    1998/08/18 03:42:10    1.8
|+++ libexec/talkd/announce.c    2000/07/06 00:01:45    1.9
|-----
Patching file libexec/talkd/announce.c using Plan A...
Hunk #1 succeeded at 160. <----- Patch Succeeded
done
$ cd /usr/src/libexec/talkd/
$ ls
CVS          announce.c  print.c      table.c      talkd.c
Makefile     announce.c.orig process.c     talkd.8      talkd.h
$ make obj && make depend && make
making /home/ericj/lsrc/src/libexec/talkd/obj
mkdep -a /home/ericj/lsrc/src/libexec/talkd/talkd.c /home/ericj/lsrc/sr
c/libexec/talkd/announce.c /home/ericj/lsrc/src/libexec/talkd/process.c
/home/ericj/lsrc/src/libexec/talkd/table.c /home/ericj/lsrc/src/libexec
/talkd/print.c
cc -O2      -c /home/ericj/lsrc/src/libexec/talkd/talkd.c
```

```

cc -O2      -c /home/ericj/lsrc/src/libexec/talkd/announce.c
cc -O2      -c /home/ericj/lsrc/src/libexec/talkd/process.c
cc -O2      -c /home/ericj/lsrc/src/libexec/talkd/table.c
cc -O2      -c /home/ericj/lsrc/src/libexec/talkd/print.c
cc -o ntalkd talkd.o announce.o process.o table.o print.o
nroff -Tascii -mandoc /home/ericj/lsrc/src/libexec/talkd/talkd.8 > talkd.cat8
$ sudo make install
install -c -s -o root -g bin -m 555 ntalkd /usr/libexec
install -c -o root -g bin -m 444 talkd.cat8 /usr/share/man/cat8/talkd.0
/usr/share/man/cat8/ntalkd.0 -> /usr/share/man/cat8/talkd.0

```

Once you have done that, you should restart that service.

## 10.16 - Tell me about this chroot() Apache?

Since OpenBSD 3.2, the Apache [httpd\(8\)](#) server has been [chroot\(2\)](#)ed by default. While this is a tremendous boost to security, it can create issues, if you are not prepared.

### What is a chroot?

A [chroot\(2\)](#)ed application is locked into a particular directory and unable to wander around the rest of the directory tree, and sees that directory as its "/" (root) directory. In the case of [httpd\(8\)](#), the program starts, opens its log files, binds to its TCP ports (though, it doesn't accept data yet), and reads its configuration. Next, it locks itself into `/var/www` and drops privileges, then starts to accept requests. This means all files served and used by Apache must be in the `/var/www` directory. This helps security tremendously -- should there be a security issue with Apache, the damage will be confined to a single directory with only "read only" permissions and no resources to cause mischief with.

### What does this mean to the user?

Put bluntly, [chroot\(2\)](#)ing Apache is something new, and many older applications and system configurations will not work as before.

- **Historic file system layouts:** Servers upgraded from older versions of OpenBSD may have web files located in user's directories, which clearly won't work in a [chroot\(2\)](#)ed environment, as [httpd\(8\)](#) can't reach the `/home` directory. Administrators may also discover their existing `/var/www` partition is too small to hold all web files. Your options are to restructure or do not use the [chroot\(2\)](#) feature. You can, of course, use symbolic links in the user's home directories pointing to subdirectories in `/var/www`, but you can NOT use links in `/var/www` pointing to other part of the file system -- that is prevented from working by the [chroot\(2\)](#)ing. Note that if you want your users to have [chroot\(2\)ed FTP access](#), this will not work, as the FTP [chroot](#) will (again) prevent you from accessing the targets of the symbolic links. A solution to this is to not use `/home` as your home directories for these users, rather use something similar to `/var/www/home`.
- **Log Rotation:** Normally, logs are rotated by renaming the old files, then sending [httpd\(8\)](#) a SIGUSR1 signal to cause Apache to close its old log files and open new ones. This is no longer possible, as [httpd\(8\)](#) has no ability to open its own log files once privileges are dropped. [httpd\(8\)](#) must be stopped and restarted:

```
# apachectl stop && apachectl start
```

There are also other strategies available, including logging to a [pipe\(2\)](#), and using an external log rotator at the other end of the [pipe\(2\)](#).

- **Existing Apache modules:** Virtually all will load, however some may not work properly in [chroot\(2\)](#), and many have issues on "`apachectl restart`", generating an error, which causes [httpd\(8\)](#) to exit.
- **Existing CGIs:** Most will NOT work as is. They may need programs or libraries outside `/var/www`. Some can be fixed by compiling so they are statically linked (not needing libraries in other directories), most may be fixed by populating the `/var/www` directory with the files required by the application, though this is non-trivial and requires considerable programming knowledge - most users will find it easier to just disable the [chroot\(2\)](#) feature until they are updated.

In some cases, the application or configuration can be altered to run within the chroot. In other cases, you will simply have to disable this feature using the `-u` option for `httpd(8)` in [/etc/rc.conf](#).

## 10.17 - I don't like the standard root shell!

The default shell for `root` on OpenBSD is [csh](#), due primarily to tradition. There is no requirement that OpenBSD have `csh(1)` for the root login (though keep reading before changing it).

Some users who come from other Unix-like operating systems find `csh(1)` unfamiliar, and ask if and how they can change it. There are a few options:

- **Don't login as `root`!** Between [su](#) and [sudo](#), there should be few reasons for users to log in as `root` for most applications after initial setup.
- **Invoke your favorite shell after login:** If you like `ksh(1)` or any other shell, just invoke it from the default shell.
- **Change the root shell:** This can be done using [chsh](#) or [vipw](#).

A traditional Unix guideline is to only use statically compiled shells for root, because if your system comes up in single user mode, non-root partitions won't be mounted and dynamically linked shells won't be able to access libraries located in the `/usr` partition. This isn't actually a significant issue for OpenBSD, as the system will prompt you for a shell when it comes up in single user mode, and the default is [sh](#). The three standard shells in OpenBSD ([csh](#), [sh](#) and [ksh](#)) are all statically linked, and thus usable in single user mode.

It is sometimes said that one should never change the root shell, though there is no reason not to in OpenBSD. But again, this shouldn't be an issue -- just don't log in as root.

## 10.18 - What else can I do with `ksh`?

In OpenBSD, [ksh](#) is [pdksh](#), the Public Domain Korn Shell, and is the same binary as [sh](#).

Users comfortable with `bash`, often used on Linux systems, will probably find [ksh](#) very familiar. `Ksh(1)` provides most of the commonly used features in `bash`, including tab completion, command line editing and history via the arrow keys, and CTRL-A/CTRL-E to jump to beginning/end of the command line. If other features of `bash` are desired, `bash` itself can be loaded via either [ports](#) or [packages](#).

The command prompt of `ksh` can easily be changed to something providing more information than the default "\$ " by setting the `PS1` variable. For example, inserting the following line:

```
export PS1='$PWD $ '
```

in your `/etc/profile` produces the following command prompt:

```
/home/nick $
```

See the file [/etc/ksh.kshrc](#), which includes many useful features and examples, and may be invoked in your user's `.profile`.

[\[FAQ Index\]](#) [\[To Section 9 - Migrating from Linux\]](#) [\[To Section 11 - Performance Tuning\]](#)



[www@openbsd.org](mailto:www@openbsd.org)

\$OpenBSD: faq10.html,v 1.94 2003/10/26 16:58:20 nick Exp \$



[\[FAQ Index\]](#) [\[To Section 10 - System Management\]](#) [\[To Section 12 - Platform-Specific Questions\]](#)

# 11 - Performance Tuning

---

## Table of Contents

- [11.1 - Networking](#)
  - [11.2 - Disk I/O](#)
  - [11.4 - Hardware Choices](#)
  - [11.5 - Why aren't we using async mounts?](#)
  - [11.6 - Tuning your monitor resolution under XFree86](#)
- 

If you run a busy server, gateway or firewall, you may wish or need to adjust some of the default parameters to get optimal performance. The [options\(4\)](#) man page talks about the kernel options presented. These options are placed in the kernel configuration file before you compile a custom kernel, and some are settable via [config\(8\)](#). For more details, see [FAQ 5](#).

## 11.1 - Networking

A parameter you may need to change for a busy server, gateway or firewall is NMBCLUSTERS. This controls the size of the kernel mbuf cluster map. On your computer, if you get messages like "mb\_map full", you need to increase the value of this parameter. If traffic on a network interface stops for no apparent reason, this may also be a sign that you need to increase the value of NMBCLUSTERS. A reasonable value on the i386 port with most 100Mbps ethernet interfaces (no matter how many the machine has) is 8192.

**option NMBCLUSTERS=8192**

The default number of NMBCLUSTERS varies from platform to platform, ranging from 256 to 2048. It is set in a platform-dependent header file unless overridden by an option line in a kernel config file.

NMBCLUSTERS can also be set using [config\(8\)](#), which eliminates the need to compile a kernel and reboot solely to change this option:

```
# config -e -o bsd.new /bsd
OpenBSD 3.3 (GENERIC) #44: Sat Mar 29 13:22:05 MST 2003
  deraadt@i386.openbsd.org:/usr/src/sys/arch/i386/compile/GENERIC
Enter 'help' for information
ukc> nmbclust
nmbclusters = 2048
ukc> nmbclust 8192
nmbclusters = 8192
ukc> quit
```

```
Saving modified kernel.
```

This will create a new kernel, `bsd.new`, in the current directory, *and* modifies the `NMBCLUSTERS` parameter of the running kernel. If all goes well, don't forget to copy `bsd.new` to `/bsd` before rebooting.

## 11.2 - Disk I/O

Disk I/O speed is a significant factor in the overall speed of your computer. It becomes increasingly important when your computer is hosting a multi-user environment (users of all kinds, from those who log-in interactively to those who see you as a file-server or a web-server.) Data storage constantly needs attention, especially when your partitions run out of space or when your disks fail. OpenBSD has several options to increase the speed of your disk operations and provide fault tolerance.

### Table Of Contents

- [CCD](#) - Concatenated Disk Driver.
- [RAID](#)
- [Filesystem Buffer](#)
- [Soft Updates](#)
- [Size of the namei\(\) cache](#)

### 11.2.1 - CCD

The first option is the use of [ccd\(4\)](#), the Concatenated Disk Driver. This allows you to join several partitions into one virtual disk (and thus, you can make several disks look like one disk). This concept is similar to that of LVM (logical volume management), which is found in many commercial Unix flavors.

If you are running GENERIC, `ccd` is already enabled (in `/usr/src/sys/conf/GENERIC`). If you have customized your kernel, you may need to return it to your kernel configuration. Either way, a line such as this should be in your configuration file:

```
pseudo-device    ccd      4          # concatenated disk devices
```

The above example gives you up to 4 `ccd` devices (virtual disks). Now you need to figure out which partitions on your real disks you want to dedicate to `ccd`. Use `disklabel` to mark these partitions as type 'ccd'. On some architectures, `disklabel` may not allow you to do this. In this case, mark them as 'ffs'.

If you are using `ccd` to gain performance by striping, note that you will not get optimum performance unless you use the same model of disks with the same `disklabel` settings.

Edit `/etc/ccd.conf` to look something like this: (for more information on configuring `ccd`, look at [ccdconfig\(8\)](#))

```
# Configuration file for concatenated disk devices
#
# ccd  ileave  flags  component devices
ccd0  16      none  /dev/sd2e /dev/sd3e
```

To make your changes take effect, run

```
# ccdconfig -C
```

As long as `/etc/ccd.conf` exists, `ccd` will automatically configure itself upon boot. Now, you have a new disk, `ccd0`, a combination of `/dev/sd2e` and `/dev/sd3e`. Just use `disklabel` on it like you normally would to make the partition or partitions you want to use. Again, don't use the 'c' partition as an actual partition that you put stuff on. Make sure your usable partitions are at least one cylinder off from the beginning of the disk.

## 11.2.2 - RAID

Another solution is [raid\(4\)](#), which will have you use [raidctl\(8\)](#) to control your raid devices. OpenBSD's RAID is based upon Greg Oster's [NetBSD port](#) of the CMU [RAIDframe](#) software. OpenBSD has support for RAID levels of 0, 1, 4, and 5.

With `raid`, as with `ccd`, support must be in the KERNEL. Unlike `ccd`, support for RAID is not found in `GENERIC`, so it must be compiled into your kernel (RAID support adds some 500K to the size of an `i386` kernel).

```
pseudo-device    raid    4        # RAIDframe disk device
```

Setting up RAID on some operating systems is confusing and painful to say the least. Not so with RAIDframe. Read the [raid\(4\)](#) and [raidctl\(8\)](#) man pages to get full details. There are many options and possible configurations available, and a detailed explanation is beyond the scope of this document.

## 11.2.3 - Filesystem Buffer

For file servers with memory to spare, you can increase `BUFCACHEPERCENT`. That is, what percentage of your RAM should you use as a file system buffer. This option may change when the Unified Buffer Cache is completed and is part of OpenBSD. In the mean time, to increase `BUFCACHEPERCENT`, you should add a line to your kernel configuration like this:

```
option BUFCACHEPERCENT=30
```

Of course you can make it as low as 5 percent (the default) or as high as 50 percent (or more.)

`BUFCACHEPERCENT` can also be set using [config\(8\)](#), as [above](#), which eliminates the need to compile a kernel solely to change this option.

## 11.2.4 - Soft updates

Another tool that can be used to speed up your system is `softupdates`. One of the slowest operations in the traditional BSD file system is updating `metainfo` (which happens, among other times, when you create or delete files and directories.) `Softupdates` attempts to update `metainfo` in RAM instead of writing to the hard disk each and every single `metainfo` update. Another effect of this is that the `metainfo` on disk should always be complete, although not always up to date. So, a system crash should not require [fsck\(8\)](#) upon boot up, but simply a background version of `fsck` that makes changes to the `metainfo` in RAM (a la `softupdates`). This means rebooting a server is much faster, as you don't have to wait for `fsck`! (OpenBSD does not have this feature yet.) You can read more about `softupdates` in the [Softupdates FAQ](#) entry.

## 11.2.5 - Size of the `namei()` cache

Note: previously, the [options\(4\)](#) manual page recommended to set the `NVNODE=integer` kernel option. This is no

longer recommended; you should now use the [sysctl\(8\)](#) command instead.

The name-to-inode translation (a.k.a., namei()) cache controls the speed of pathname to [inode\(5\)](#) translation. By default, this cache has  $NPROC * (80 + NPROC / 8)$  entries. NPROC is set to  $20 + 16 * MAXUSERS$ ; see the [config\(8\)](#) manual page for an explanation on the `maxusers` kernel configuration parameter. A reasonable way to derive a value for the cache, should a large number of namei() cache misses be noticed with a tool such as [systat\(1\)](#), is to examine the system's current computed value with [sysctl\(8\)](#), (which calls this parameter "`kern.maxvnodes`") and to increase this value until either the namei() cache hit rate improves or it is determined that the system does not benefit substantially from an increase in the size of the namei() cache. After the value has been determined, you can set it at system startup time with [sysctl.conf\(5\)](#).

## 11.4 - Hardware choices

*(Note- this section is heavily centered around the i386, or PC, architecture. That is to say... other architectures don't give you quite as many choices!)*

The performance of your applications depends heavily on your OS and the facilities it provides. This may be part of the reason that you are using OpenBSD. The performance of your applications also depends heavily on your hardware. For many folks, the Price/Performance ratio of a brand new PC with a Intel Pentium IV or AMD Athlon processor is much better than the Price/Performance ratio of a Sun UltraSparc 60! Of course, the price of OpenBSD can't be beaten.

If you are shopping for a new PC, whether you are buying it piece by piece or completely pre-built, you want to make sure first that you are buying reliable parts. In the PC world, this is not easy. **Bad or otherwise unreliable or mismatched parts can make OpenBSD run poorly and crash often.** The best advice we can give is to be careful, and buy brands and parts that have been reviewed by an authority you trust. Sometimes, when you skimp on the price of a PC, you lose in quality!

There are certain things that will help bring out the maximum performance of your hardware:

- **Use multiple disks.** Instead of buying one large disk, buy multiple smaller disks. While this may cost more, distributing the load over multiple spindles will decrease the amount of time necessary to access data on the disks. And, with more spindles, you will get more reliability and faster data access with RAID.
- **Use SCSI if you need very high disk IO speeds.** IDE disks normally run at 5400 RPM to 7200 RPM. Using high end IDE disks, it may be unreasonable to expect more than 15 to 20 megabytes per second of throughput from a single disk. Using high end SCSI disks (higher cost 10k RPM to 15k RPM disks), you can achieve performance higher than this. Conversely, if you are using medium or low end SCSI disks, this is a waste of money, and IDE will serve you just as well, if not better.

If you are building a server, and you need more than one drive, you may want to consider SCSI. IDE limits you to two disks per controller. Concurrent access to these two disks may have a negative impact on the I/O performance of these disks. Wide SCSI limits you to 15 per controller, and has better support for concurrent access than IDE. While SCSI costs more, the flexibility and performance can justify these costs in some environments.

- **Use SDRAM instead of DRAM.** This option applies mainly to PCs. Most other architectures don't give you a choice of what kind of RAM you can use. Several PCs still do. You will get better performance with SDRAM versus DRAM (SIMMs). If your system supports RDRAM, DDR or some other new type of RAM, then you are even further ahead...
- **Use ECC or parity RAM.** Parity adds some functionality to see if the data in RAM has been corrupted. ECC extends this functionality and attempts to correct some bit corruption errors on the fly. This option applies mainly to PCs. Most other architectures simply require parity or ECC capable RAM. Several non-PC computers won't even boot with non-parity RAM. If you aren't using ECC/parity RAM, you may get data corruption and other abnormalities. Several manufacturers of "cheap PC RAM" don't even make an ECC variety! This will help you avoid them! PC manufacturers

often sell several product lines, divided around "servers" and "workstations." The servers will incorporate ECC RAM into their architecture. Unix workstation manufacturers have been using parity (and now ECC) for several years in all of their product lines.

- **Avoid ISA devices.** While most folks avoid ISA devices because they are generally hard to configure and out of date, there are still plenty in existence. If you are using the ISA bus for your disk or network controllers, (or even worse, for both) remember that the ISA bus itself can be a performance bottleneck. If you need speed, look into PCI. Of course, there are still several ISA bus cards that work just fine. Unfortunately, most of these are sound cards and serial port cards.
- **Avoid cheap PCI network adapters.** OpenBSD supports a plethora of cheap PCI network adapters. These adapters work great in home systems, and also low or moderate throughput business and research environments. But, if you need high throughput and low impact on your server, you are better off buying a quality PCI network adapter. Unfortunately, some expensive brand adapters (such as the 3com XL series) are not much better than the cheap adapters. One favourite 10/100Mbps adapter is the Intel EtherExpress PRO/100.

## 11.5 - Why aren't we using async mounts?

Question: "I simply do "mount -u -o async /" which makes one package I use (which insists on touching a few hundred things from time to time) usable. Why is async mounting frowned upon and not on by default (as it is in some other unixen)? Isn't it a much simpler, and therefore, a safer way of improving performance in some applications?"

Answer: "Async mounts is indeed faster than sync mounts, but they are also less safe. What happens in case of a power failure? Or a hardware problem? The quest for speed should not sacrifice the reliability and the stability of the system. Check the man page for [mount\(8\)](#)."

```
async    All I/O to the file system should be done asynchronously.
         This is a dangerous flag to set since it does not guaran-
         tee to keep a consistent file system structure on the
         disk.  You should not use this flag unless you are pre-
         pared to recreate the file system should your system
         crash.  The most common use of this flag is to speed up
         restore(8) where it can give a factor of two speed in-
         crease.
```

On the other hand, when you are dealing with temp data that you can recreate from scratch after a crash, you can gain speed by using a separate partition for that data only, mounted async. Again, do this *only if* you don't mind the loss of all the data in the partition when something goes wrong. For this reason, [mfs\(8\)](#) partitions are mounted asynchronously, as they will get wiped and recreated on a reboot anyway.

## 11.6 - Tuning your monitor resolution under XFree86

Getting an X server working at an acceptable resolution with many multi-sync monitors is possible. If anyone has tried to do this with the standard xf86config or XF86Setup utilities, they probably didn't get the best possible results. One of the more painful aspects is simply getting your monitor running with your preferred resolution, and then getting the vertical scan rate set to at least 72-75 Hz, a rate where the screen flicker is much less visible to humans. Conversely, what if you are trying to set the vertical scan rate so it is very low? You can set it at 50 Hz so that it can be captured on to video without flicker, but the methods to do this are non-obvious with the standard XFree86 tools and documentation.

Finally, at the resolutions many people normally use with inexpensive VGA monitors (800x600, 1024x768, 1152x900, 1280x1024), it is possible (at least on newer monitors) to use vertical scan rates of 85Hz and above, to achieve an extremely clean, palatable picture. The XFree86 X server has a mechanism which allows you to describe in detail the video mode you want to use, this is the ModeLine. A ModeLine has four sections, a single number for the pixel clock, four numbers for horizontal timings, four

numbers for vertical timings, and an optional section with a list of flags specifying other characteristics of the mode (such as Interlace, DoubleScan, and more... see the XF86Config(5) manual page for more ModeLine details).

Generating a ModeLine is a black art... Luckily, there are several scripts which can do this for you. One is [Colas XFree86 ModeLine Generator](#). Another is [The XFree86 Modeline Generator](#) hosted at SourceForge, and there are several others available on [Freshmeat](#). Before you can use these ModeLine generators, you need to figure out the vertical and horizontal sync limits for your monitor. This is often documented in the manual, or on the manufacturer's web site. If you can't find either of those, simply search the web for the monitor make and model, several people have been kind enough to compile lists with this information.

For example, say you have a Dell D1226H monitor. You searched in agony at Dell's web site to find that it has a 30-95 kHz horizontal scan range, and a 50-160 Hz vertical scan range. Visit the ModeLine generator page, enter this information. Next, you need to enter the minimum vertical scan rate you want. Any rate at or above 72 Hz should generally have low visible flicker. As you go higher, the clearer and crisper your screen image becomes.

With all of these bits of information, the script will generate a ModeLine for every possible 4x3 resolution which your monitor can support, above the minimum vertical scan rate which you enter. If someone enters the Dell specs above and a 75 Hz vertical scan minimum, the script gives out something like the following:

```
ModeLine "320x240" 20.07 320 336 416 448 240 242 254 280 #160Hz
ModeLine "328x246" 20.86 328 344 424 456 246 248 260 286 #160Hz
...
ModeLine "816x612" 107.39 816 856 1056 1136 612 614 626 652 #145Hz
ModeLine "824x618" 108.39 824 864 1064 1144 618 620 632 658 #144Hz
ModeLine "832x624" 109.38 832 872 1072 1152 624 626 638 664 #143Hz
...
ModeLine "840x630" 109.58 840 880 1080 1160 630 632 644 670 #141Hz
ModeLine "848x636" 110.54 848 888 1088 1168 636 638 650 676 #140Hz
...
ModeLine "1048x786" 136.02 1048 1096 1336 1432 786 788 800 826 #115Hz
ModeLine "1056x792" 136.58 1056 1104 1344 1440 792 794 806 832 #114Hz
ModeLine "1064x798" 137.11 1064 1112 1352 1448 798 800 812 838 #113Hz
...
ModeLine "1432x1074" 184.07 1432 1496 1816 1944 1074 1076 1088 1114 #85Hz
ModeLine "1576x1182" 199.86 1576 1648 2008 2152 1182 1184 1196 1222 #76Hz
ModeLine "1584x1188" 198.93 1584 1656 2016 2160 1188 1190 1202 1228 #75Hz
```

Now, this monitor claims to do 1600x1200 @ 75 Hz, but the script does not say this is within 75 Hz. So, if you really want exactly 1600x1200, go down a notch with your minimum vertical rate... (Here, we go down to 70 Hz)

```
ModeLine "1592x1194" 197.97 1592 1664 2024 2168 1194 1196 1208 1234 #74Hz
ModeLine "1600x1200" 199.67 1600 1672 2032 2176 1200 1202 1214 1240 #74Hz
ModeLine "1608x1206" 198.65 1608 1680 2040 2184 1206 1208 1220 1246 #73Hz
ModeLine "1616x1212" 197.59 1616 1688 2048 2192 1212 1214 1226 1252 #72Hz
ModeLine "1624x1218" 199.26 1624 1696 2056 2200 1218 1220 1232 1258 #72Hz
ModeLine "1632x1224" 198.15 1632 1704 2064 2208 1224 1226 1238 1264 #71Hz
ModeLine "1640x1230" 199.81 1640 1712 2072 2216 1230 1232 1244 1270 #71Hz
ModeLine "1648x1236" 198.64 1648 1720 2080 2224 1236 1238 1250 1276 #70Hz
```

Here, we see the monitor really does 1600x1200 @ 74 Hz when the dot clock (bandwidth) is limited to 200MHz. Set the bandwidth according to the limits defined by the monitor.

Once you have your ModeLines, put them into your `/etc/X11/XF86Config` file. Comment out the old ModeLines, so that you can use them again if the new ones don't work. Next, choose what resolution you actually want to run at. First, figure out if X is running in accelerated mode (which it does with most video cards), so you know which "Screen" section of the XF86Config to modify. Or, just modify all of the Screen sections.

```

Section "Screen"
    Driver      "Accel"
    Device      "Primary Card"
    Monitor     "Primary Monitor"
    DefaultColorDepth 32
    SubSection "Display"
        Depth    32
        Modes    "1280x1024" "1024x768"
    EndSubSection

```

The first resolution you see after the "Modes" keyword is the resolution that X is going to start in. By pressing CTRL-ALT-KEYPAD MINUS, or CTRL-ALT-KEYPAD PLUS, you can switch between any resolutions that you list here. According to the section above, X will try to start in 32-bit color mode (via the DefaultColorDepth directive, without it X will start in 8-bit color mode.) The first resolution it will try to use is 1280x1024 (it follows the order of the Modes line.) Note that "1280x1024" is just a label for the values in the ModeLine.

Note that the ModeLine generator script has options to relax its timings for older or smaller monitors, and also has the ability to provide ModeLines for specific resolutions. Depending on the type of hardware you have, it may not be very easy to use with the default options. If the picture is too tall, too wide, or too small, or is shifted horizontally or vertically, and the controls of the monitor aren't enough to correct its appearance, once can use `xvidtune(1)` to adjust the ModeLine to better fit with the monitor's timings.

On most modern monitors, there is no fixed limit on the bandwidth, thus they are often not listed anymore in the specs. What happens is that the more you go up in bandwidth, the fuzzier the screen image becomes. So you may want to put in the bandwidth of your card (also named "dotclock") to test (you cannot damage your monitor this way), and go progressively down in BW down to have a nice crisp image.

If this seems needlessly complex, that's because it is. XFree86 4.0 addresses this, and makes this process much easier since it has several built-in modes and is capable of reading back capabilities from "plug and play" monitors through DDC and DDC2.

You can download the Colas XFree86 ModeLine Generator script at: <http://koala.ilog.fr/ftp/pub/Klone/>. You need to grab the Klone interpreter, and compile it. It is in the ports as `lang/klone`. The scripts exist under the scripts directory in the Klone distribution. (The port installs them to `/usr/local/lib/klone/scripts`.)

There are two versions of the script included, the first is a CGI version identical to the web page above. The second is a non-CGI version which will take your complete XF86Config file, decode the monitor specs that you entered into `xf86config/XF86Setup` (Now, think, did you actually enter the specs for your monitor or just choose generic ones?), and fix the existing ModeLines accordingly.

[\[FAQ Index\]](#) [\[To Section 10 - System Management\]](#) [\[To Section 12 - Platform-Specific Questions\]](#)



[www@openbsd.org](mailto:www@openbsd.org)

\$OpenBSD: faq11.html,v 1.46 2003/10/16 00:48:14 nick Exp \$



[\[FAQ Index\]](#) [\[To Section 11 - Performance Tuning\]](#) [\[To Section 14 - Disk Setup\]](#)

## 12 - Platform-Specific Questions

---

### Table of Contents

- [12.1 - General hardware notes](#)
    - [12.1.1 - PCI](#)
    - [12.1.2 - ISA](#)
  - [12.2 - DEC Alpha](#)
  - [12.3 - HP 9000 series 300, 400](#)
  - [12.4 - HP Precision Architecture \(PA-RISC\)](#)
  - [12.5 - i386](#)
    - [12.5.1 - ISA NICs](#)
    - [12.5.2 - OpenBSD won't boot on my 80386 system](#)
    - [12.5.3 - My dmesg shows multiple devices sharing the same interrupt](#)
  - [12.6 - Mac68k](#)
    - [12.6.1 - My Mac68k system doesn't seem to work](#)
    - [12.6.2 - Why is my Mac68k losing so much time?](#)
    - [12.6.3 - My Mac68k system won't work with two disks](#)
    - [12.6.4 - The installer crashed during install](#)
  - [12.7 - MacPPC](#)
  - [12.8 - MVME68k](#)
  - [12.9 - SPARC](#)
  - [12.10 - UltraSPARC](#)
    - [12.10.1 - My UltraSPARC won't boot from the floppy image](#)
  - [12.11 - DEC VAX](#)
- 

## 12.1 - General hardware notes

### 12.1.1 - PCI devices

- PCI devices are mostly self-configuring -- the computer and OS will allocate resources to the cards as required.
- Interrupts can be shared on the PCI bus. Not only can they be, the system will often perform better when the IRQs are shared, especially on i386 systems.
- There are several different PCI bus standards. You will occasionally find a PCI2.2 specification card that will just not work in a PCI2.1 specification system. Also, many cards with on-board bridges (such as, multi-port network cards) will not work well in older systems.
- The PCI bus supports two levels of signaling, 3.3v and 5v. Cards that work with 3.3v signaling have a second notch cut in their PCI connector. Most PCI cards use 5v signaling, which is used by most computers. The Soekris single-board computers (Net45x1 and Net4801) are commonly-encountered computers that only support 3.3v signaling.

## 12.1.2 - ISA devices

- ISA devices cannot share resources, and in general, must be manually configured to settings that don't conflict with other devices in the system.
- Some ISA devices are "Plug and Play" ([isapnp\(4\)](#)) -- if you have any problem with these devices, though, verify their configuration in your [dmesg\(8\)](#). ISAPnP doesn't always work as desired.
- In general, if you have a choice, most people are best advised to avoid ISA cards in favor of PCI. ISA cards are more difficult to configure and have a much greater negative impact on the system's performance.

## 12.2 - DEC Alpha

[nothing yet]

## 12.3 - HP300

[nothing yet]

## 12.4 - HPPA

[nothing yet]

## 12.5 - i386

### 12.5.1 - ISA NICs

As OpenBSD runs well on older hardware, users often will end up using ISA NICs on OpenBSD systems. ISA hardware requires much more configuration and understanding than does PCI hardware. In general, you can't just stuff the card in the computer and expect it to magically work. In many machines, if your ISA device is not in a "Plug 'n' Play" (PNP) mode, you must reserve the resources the card uses in the system's BIOS.

#### 3Com 3C509B ep(4)

This is an excellent performing ISA NIC, supported by the [ep\(4\)](#) driver. The 'B' version can be distinguished from the non-B version by labeling on the card and by the larger "main" chip on the board (approximately 2.5cm on a side for the 'B' version, vs. 2cm on a side on the older version), and will provide better performance on a loaded or dual network card system. The 3C509B ships configured in a PNP mode, which unfortunately does not comply with standards, and causes problems in OpenBSD's [isapnp\(4\)](#) support. The adapter is picked up first as a non-PNP device, then again after the PNP support comes on-line, resulting in an extra NIC showing in the dmesg. This may work fine, or it may cause other problems. It is highly recommended that the 3C509B cards have PNP mode disabled and manually configured to non-conflicting settings using the 3Com DOS-based configuration utilities before configuration.

The ep(4) driver will pick the cards up at any hardware combination that does not conflict with other devices in the system.

If you have multiple 3C509 cards in your system, it is recommended that you label the cards' spine with the MAC address, and use the dmesg to identify which is which.

Note that the 3C509, the 3C905 and the 3C590 are often confused. The 3C509 is a 10Mbps ISA card, the 3C905 and 3C590 are PCI cards.

## NE2000

The original NE2000 NIC was developed in the mid-1980s by Novell. Since then, many manufacturers have produced cards that are very similar, which are generally called NE2000-compatibles, or clones. Performance of these clone cards varies greatly. While some older NE2000-compatible cards performed very well, many of the currently-available ones perform poorly. NE2000-compatibles are supported by the [ne\(4\)](#) driver in OpenBSD.

OpenBSD will handle some ISAPNP-capable NE2000-compatible cards well if the ISAPNP mode is turned on. Other cards will have to be set using either jumpers or a DOS-based configuration utility. Unfortunately, as the original NE2000 cards did not have software configuration or ISAPNP support, there are no standards for this -- you need the utility that will have been originally supplied with your specific card. This can often be difficult to obtain.

The ne(4) driver supports three configurations of the ISA NE2000 card in the GENERIC OpenBSD kernel:

```
ne0:  port 0x240 irq 9
ne1:  port 0x300 irq 10
ne2:  port 0x280 irq 9
```

If these settings are not acceptable, you can adjust them using [User Kernel Configuration \(UKC\)](#) or by [building a customized kernel](#).

Note that the ne(4) driver is fairly "dumb" -- only the I/O port is probed, if any of the above I/O addresses is detected, the corresponding IRQ is *assumed*. [dmesg\(8\)](#) will not reflect the actual IRQ of the adapter in the case of ISA ne(4) drivers. If this is not the actual IRQ your card is set to, it will not work.

Note that there are non-ISA cards that use the ne(4) driver -- PCI and PCMCIA ne(4) cards exist. These notes do not apply to them, these devices are auto-configuring.

## 12.5.2 - OpenBSD won't boot on my 80386 (or 80386sx) system!

### 80386sx

The 80386sx has a maximum addressing range of 16M, which is at the very low end of OpenBSD/i386's support. Most 80386sx systems can't support more than 8M of RAM, which places them in the "For Experts Only" category, as some non-trivial steps and a second computer are required to get going. Also, see the next section:

### 80386

There is a bug that prevents OpenBSD from booting on a 80386 or 80386sx system in OpenBSD 3.3 and many earlier versions. It can be worked around by replacing the 80386 chip with any of the 80486-like accelerator retrofit chips that exist (or running [current](#)). Again, be aware that this is a very small amount of processor for a crypto-intensive operating system like OpenBSD. You aren't likely to be happy with the performance of such a machine for general use.

## 12.5.3 - My dmesg shows multiple devices sharing the same Interrupt (IRQ)!

This is entirely acceptable, and in fact, even desirable for PCI devices. This is a design feature of the PCI bus. Some people will say that sharing interrupt requests (IRQs) is bad, however they are either confusing the situation with the ISA bus (where IRQ

sharing is not permitted), or past experience with broken hardware or software.

ISA devices can not share IRQs. If you find ISA devices sharing IRQs, you must correct this problem.

## 12.6 - Mac68k

### 12.6.1 - My Mac68k system doesn't seem to work!

Unfortunately, we have a small number of different Mac68k machines in the hands of OpenBSD developers, and thus, only a few are known to work well at this moment. If you can help restore support to currently broken systems, your code would be welcome!

### 12.6.2 - Why is my Mac68k losing so much time?

This is caused by a hardware bug. OpenBSD uses clock interrupts to keep track of the current time, but these interrupts have the lowest priority in the [Mac68k](#) architecture. So, under heavy load, (such as disk or network activity) clock interrupts will be lost and the Unix clock will not advance as it should. [MacPPC](#) systems do not have this issue.

MacOS gets around the time problem by always reading the hardware clock. OpenBSD only reads the hardware clock at boot time and thereafter ignores it. You may notice that, at shutdown, the kernel is not confident enough to write the Unix time back into the hardware clock because this time loss problem is well known.

A simple solution is to run `rdate(8)` on a regular basis, by having a crontab entry for it. Another good place to launch [rdate\(8\)](#) is in your `/etc/ppp/ppp.linkup` file if you are not permanently connected and are a PPP user.

See also: <http://www.macbsd.com/macbsd/macbsd-docs/faq/faq-3.html#ss3.17>

### 12.6.3 - My Mac68k system won't work with two disks

Yes, unfortunately, this is a known problem. This usually shows itself by crashes shortly after the system goes multi-user, and the crash may not be obviously related to the disk system. The solution is to only use one drive on your Mac68k systems. A proper fix would be welcomed!

### 12.6.4 - The installer crashed during install

The Mac68k installer running on MacOS will not install files to a "large" partition. If any partition you are installing to is more than around 500M in size, you can expect the following strange error:

```
Error on SCSIRead(), #5
pos = 0, i = 22, fs = /
alloccblk: can't find blk in cyl
```

The solution to this is to first install a minimal system in a "small" root partition, then boot OpenBSD and relocate things as desired.

So, let's say you want a 200M / partition. Create the root partition, create the other partitions you want, newfs them all using the MacOS utilities. Install `etc33.tgz` and `base33.tgz` to this / partition.

Mount your other partitions on a temporary mount point, and copy over the directories you want to them, as demonstrated [here](#).

Now, modify /etc/fstab, reboot, and unpack the rest of the \*.tgz files as documented [here](#).

Following this process, any size can be achieved for the non-root partitions.

## 12.7 - MacPPC

[nothing yet]

## 12.8 - MVME68k

[nothing yet]

## 12.9 - SPARC

[nothing yet]

## 12.10 - UltraSPARC (sparc64)

### 12.10.1 - My UltraSPARC won't boot from the floppy image

Only the Ultra 1/1e and Ultra 2 can boot *any* OS from floppy disk. Use CD-ROM, Miniroot, or network boot to do your installation instead.

## 12.11 - DEC VAX

[nothing yet]

[\[FAQ Index\]](#) [\[To Section 11 - Performance Tuning\]](#) [\[To Section 14 - Disk Setup\]](#)



[www@openbsd.org](mailto:www@openbsd.org)

\$OpenBSD: faq12.html,v 1.44 2003/10/10 00:37:55 nick Exp \$



[\[FAQ Index\]](#) [\[To Section 12 - Platform-Specific Questions\]](#)

## 14 - Disk Setup

---

### Table of Contents

- [14.1 - Using OpenBSD's disklabel](#)
  - [14.2 - Using OpenBSD's fdisk](#)
  - [14.3 - Adding extra disks in OpenBSD](#)
  - [14.4 - How to swap to a file](#)
  - [14.5 - Soft Updates](#)
  - [14.7 - What are the issues regarding large drives with OpenBSD?](#)
  - [14.8 - Installing Bootblocks - i386 specific](#)
  - [14.9 - Preparing for disaster: Backing up and Restoring from tape.](#)
  - [14.10 - Mounting disk images in OpenBSD](#)
  - [14.11 - Help! I'm getting errors with PCIIDE!](#)
  - [14.13 - RAID options with OpenBSD](#)
- 

## 14.1 - Using OpenBSD's disklabel

### Table of Contents

- [What is disklabel?](#)
- [disklabel during the OpenBSD install](#)
- [Common disklabel uses.](#)

### What is disklabel?

First be sure to read the [disklabel\(8\)](#) man page.

Disklabels are created to allow an efficient interface between your disk and the disk drivers contained within the kernel. Labels hold certain information about your disk, like your drive geometry and information about your filesystems. This is then used by the bootstrap program to load the drive and to know where filesystems are contained on the drive. Labels are also used in conjunction with the filesystems to create a more efficient environment. You can read more in-depth information about disklabel by reading the [disklabel\(5\)](#) man page.

As an additional gain, using disklabel helps overcome architecture limitations on disk partitioning. For example, on i386, you can only have 4 primary partitions. (Partitions that other operating systems, such as Windows NT or DOS can see.) With [disklabel\(8\)](#), you use one of these 'primary' partitions to store \*all\* of your OpenBSD partitions (eg. 'swap', '/', '/usr' and '/var'). And you still have 3 more partitions available for other OSs!

### disklabel during OpenBSD's install

One of the major parts of OpenBSD's install is your initial creation of labels. This comes (for i386 users) directly after using [fdisk\(1\)](#). During the install you use disklabel to create your separate labels which will contain your separate mountpoints. During the install, you can set your mountpoints from within [disklabel\(8\)](#), but this isn't completely necessary considering you will be prompted later to confirm you choices. But it does make your install go just a little smoother.

Since this is during the install you won't have any existing labels, and they will need to be created. The first label you will create is the label 'a'. This label SHOULD be your where / will be mounted. You can see recommended partitions that should be created and their sizes by reading [FAQ 4, Space Needed](#). For servers it is recommended that you create at least these label's separately. For desktop users creating one mountpoint at / will probably suffice. When initially creating your root partition ( 'a' label ), keep in mind that you will need SOME space left for your swap label. Now that the basics have been explained, here is an

example of using disklabel during an install. In this first example it is assumed that OpenBSD will be the only operating system on this computer, and that a full install will be done.

If this disk is shared with other operating systems, those operating systems should have a BIOS partition entry that spans the space they occupy completely. For safety, also make sure all OpenBSD file systems are within the offset and size specified in the 'A6' BIOS partition table. (By default, the disklabel editor will try to enforce this). If you are unsure of how to use multiple partitions properly (ie. separating /, /usr, /tmp, /var, /usr/local, and other things) just split the space into a root and swap partition for now.

```
# using MBR partition 3: type A6 off 63 (0x3f) size 4991553 (0x4c2a41)
```

Treating sectors 63-16386300 as the OpenBSD portion of the disk.  
You can use the 'b' command to change this.

Initial label editor (enter '?' for help at any prompt)

```
> d a
> a a
offset: [63] <Enter>
size: [16386237] 64M
Rounding to nearest cylinder: 131040
FS type: [4.2BSD] <Enter>
mount point: [none] /
fragment size: [1024] <Enter>
block size: [8192] <Enter>
cpg: [16] <Enter>
> a b
offset: [131103] <Enter>
size: [16255197] 64M
Rounding to nearest cylinder: 131040
FS type: [swap] <Enter>
```

At this point we have created a 64M root partition mounted at /, and a 64Meg swap partition. Notice that the offset starts at sector 63. This is what you want. When it comes to the size, disklabel will show your size in sectors, however, you don't need to enter sizes in the same format. Like the example above you can enter sizes in the manner of *64 Megabytes = 64M* and *2 Gigabytes = 2G*. Disklabel will then round to the nearest cylinder. In the example above you will also notice that disklabel assumes that label 'b' will be a swap. This is a correct assumption as the GENERIC kernel is set to look for swap on label 'b', and you should just follow this guideline and use 'b' as your swap area.

The next example will take you through the creation of two more labels. This means that it's not a complete install, as the size of these won't be enough to install OpenBSD to its fullest. Showing the creation of all the partitions would just be repetitive.

```
> a d
offset: [262143] <Enter>
size: [16124157] 64M
Rounding to nearest cylinder: 131040
FS type: [4.2BSD] <Enter>
mount point: [none] /tmp
fragment size: [1024] <Enter>
block size: [8192] <Enter>
cpg: [16] <Enter>
> a e
offset: [393183] <Enter>
size: [15993117] 64M
Rounding to nearest cylinder: 131040
FS type: [4.2BSD] <Enter>
mount point: [none] /var
fragment size: [1024] <Enter>
block size: [8192] <Enter>
cpg: [16] <Enter>
```

In the above example, there are two things you might notice. One being that the offset is automatically figured out for you to be the next in order. When doing an install of this sort, you won't need to mess with changing the offsets at all. Another difference you might notice will be that label 'c' has been skipped. This is done for a reason, which is that label 'c' is a label that represents the whole disk. For this reason you shouldn't deal with label 'c' in any way.

Once all your labels have been created all that's left to do is write the labels to disk, and move on in the installation process. To write everything and quit disklabel (and continue with the install) do:

```
> w
```

```
> q
```

**\*NOTE\*** - For users with large drives. If your bios isn't able to support a drive of that size OpenBSD cannot support it either. Otherwise OpenBSD should be able to handle your drive just fine. If you are in a situation where your bios doesn't support your drive, you can try Maxtor EZ-Drive or other similar overlay product.

## Common uses for disklabel(8)

Once your system is installed, you shouldn't need to use disklabel too often. But some times you will need to use disklabel when adding, removing or restructuring your disks. One of the first things you will need to do is view your current disklabel. To do this, simply type:

```
# disklabel wd0 >----- Or whatever disk device you'd like to view

# using MBR partition 3: type A6 off 64 (0x40) size 16777152 (0xffffc0)
# /dev/rwd0c:
type: ESDI
disk:
label: TOSHIBA MK2720FC
flags:
bytes/sector: 512
sectors/track: 63
tracks/cylinder: 16
sectors/cylinder: 1008
cylinders: 2633
total sectors: 2654064
rpm: 3600
interleave: 1
trackskew: 0
cylinderskew: 0
headswitch: 0          # milliseconds
track-to-track seek: 0 # milliseconds
drivedata: 0

16 partitions:
#      size  offset  fstype  [fsize bsize  cpg]
#  a: 2071440  65583  4.2BSD  1024  8192   16  # (Cyl.  65*- 2120)
#  b:  65520    63      swap                # (Cyl.  0*- 65)
#  c: 2654064    0   unused                # (Cyl.  0 - 2632)
#  j:  512001 2137023  4.2BSD  1024  8192   16  # (Cyl. 2120*- 2627*)
```

The above command simply allows you to view the existing disklabel, and assuring that you dont mess anything up. ( Which we all need sometimes. ) But to be able to make changes you must use the -E option with disklabel like so:

```
# disklabel -E wd0
```

This will bring you to a prompt, the same as the one that you used during the OpenBSD install. Probably the single most important command at this prompt is '?'. This will give you a list of possible options pertaining to disklabel. You can even view the entire [disklabel\(8\)](#) man page with the 'M' command. From this prompt, you will do all of your adding, deleting and changing of partitions. For additional information read the [disklabel\(8\)](#) man page.

## 14.2 - Using fdisk

First be sure to check the fdisk man page. [fdisk\(8\)](#)

Fdisk is a program to help with the maintenance of your partitions. This program is used at install time to set up your OpenBSD partition (this partition can contain several labels, each with filesystems/swap/etc.). It can divide space on your drives and set one active. This program will usually be used in Single User Mode ( boot -s ). Fdisk also sets the MBR on your various hard disks.

For installation purposes, most times you'll only need **ONE** OpenBSD partition, and then using disklabel to put a swap and a filesystem on it.

To just view your partition table using fdisk, use:

```
# fdisk fd0
```

Which will give an output similar to this:

```

Disk: fd0          geometry: 80/2/18 [2880 sectors]
Offset: 0         Signatures: 0xAA55,0x0
      Starting      Ending
  #: id  cyl  hd sec -   cyl  hd sec [   start -   size]
-----
*0: A6   0   0   1 -   79   1  18 [   0 -   2880] OpenBSD
 1: 00   0   0   0 -    0   0   0 [   0 -    0] unused
 2: A7   0   0   2 -   79   1  18 [   1 -  2879] NEXTSTEP
 3: 00   0   0   0 -    0   0   0 [   0 -    0] unused

```

In this example we are viewing the fdisk output of floppy drive. We can see the OpenBSD partition (A6) and its size. The \* tells us that the OpenBSD partition is a bootable partition.

In the previous example we just viewed our information. What if we want to edit our partition table? Well, to do so we must use the **-e** flag. This will bring up a command line prompt to interact with fdisk.

```

# fdisk -e wd0
Enter 'help' for information
fdisk: 1> help
      help          Command help list
      manual        Show entire OpenBSD man page for fdisk
      reinit        Re-initialize loaded MBR (to defaults)
      setpid        Set the identifier of a given table entry
      disk          Edit current drive stats
      edit          Edit given table entry
      flag          Flag given table entry as bootable
      update        Update machine code in loaded MBR
      select        Select extended partition table entry MBR
      print         Print loaded MBR partition table
      write         Write loaded MBR to disk
      exit          Exit edit of current MBR, without saving changes
      quit          Quit edit of current MBR, saving current changes
      abort         Abort program without saving current changes

fdisk: 1>

```

It is perfectly safe in fdisk to go in and explore, just make sure to answer **N** to saving the changes and **\*DON'T\*** use the **write** command.

Here is an overview of the commands you can use when you choose the **-e** flag.

- **help** Display a list of commands that fdisk understands in the interactive edit mode.
- **reinit** Initialize the currently selected, in-memory copy of the boot block.
- **disk** Display the current drive geometry that fdisk has probed. You are given a chance to edit it if you wish.
- **setpid** Change the partition identifier of the given partition table entry. This command is particularly useful for reassigning an existing partition to OpenBSD.
- **edit** Edit a given table entry in the memory copy of the current boot block. You may edit either in BIOS geometry mode, or in sector offsets and sizes.
- **flag** Make the given partition table entry bootable. Only one entry can be marked bootable. If you wish to boot from an extended partition, you will need to mark the partition table entry for the extended partition as bootable.
- **update** Update the machine code in the memory copy of the currently selected boot block.
- **select** Select and load into memory the boot block pointed to by the extended partition table entry in the current boot block.
- **print** Print the currently selected in-memory copy of the boot block and its MBR table to the terminal.
- **write** Write the in-memory copy of the boot block to disk. You will be asked to confirm this operation.
- **exit** Exit the current level of fdisk, either returning to the previously selected in-memory copy of a boot block, or exiting the program if there is none.
- **quit** Exit the current level of fdisk, either returning to the previously selected in-memory copy of a boot block, or exiting the program if there is none. Unlike exit it does write the modified block out.
- **abort** Quit program without saving current changes.

## 14.3 - Adding extra disks in OpenBSD

Well once you get your disk installed **PROPERLY** you need to use [fdisk\(8\)](#) (*i386 only*) and [disklabel\(8\)](#) to set up your disk in OpenBSD.

For i386 folks, start with fdisk. Other architectures can ignore this. In the below example we're adding a third SCSI drive to the system.

```
# fdisk -i sd2
```

This will initialize the disk's "real" partition table for exclusive use by OpenBSD. Next you need to create a disklabel for it. This will seem confusing.

```
# disklabel -e sd2

(screen goes blank, your $EDITOR comes up)
type: SCSI
...bla...
sectors/track: 63
total sectors: 6185088
...bla...
16 partitions:
#      size  offset  fstype  [fsize bsize  cpg]
c:  6185088      0  unused      0    0
d:  1405080     63  4.2BSD    1024  8192    16  # (Cyl.  0*- 1393*)
e:  4779945  1405143  4.2BSD    1024  8192    16  # (Cyl. 1393*- 6135)
```

First, ignore the 'c' partition, it's always there and is for programs like disklabel to function! For normal operations, fsize should always be 1024, bsize should always be 8192, and cpg should always be 16. Fstype is 4.2BSD. Total sectors is the total size of the disk. Say this is a 3 gigabyte disk. Three gigabytes in disk manufacturer terms is 3000 megabytes. So divide 6185088/3000 (use [bc\(1\)](#)). You get 2061. So, to make up partition sizes for a, d, e, f, g, ... just multiply X\*2061 to get X megabytes of space on that partition. The offset for your first new partition should be the same as the "sectors/track" reported earlier in disklabel's output. For us it is 63. The offset for each partition afterwards should be a combination of the size of each partition and the offset of each partition (Except the 'c' partition, since it has no play into this equation.)

Or, if you just want one partition on the disk, say you will use the whole thing for web storage or a home directory or something, just take the total size of the disk and subtract the sectors per track from it. 6185088-63 = 6185025. Your partition is

```
d:  6185025      63  4.2BSD    1024  8192    16
```

**If all this seems needlessly complex, you can just use disklabel -E to get the same partitioning mode that you got on your install disk!** There, you can just use "96M" to specify "96 megabytes". (Or, if you have a disk big enough, 96G for 96 gigs!) Unfortunately, the -E mode uses the BIOS disk geometry, not the real disk geometry, and often times the two are not the same. To get around this limitation, type 'g d' for 'geometry disk'. (Other options are 'g b' for 'geometry bios' and 'g u' for geometry user, or simply, what the label said before disklabel made any changes.)

That was a lot. But you are not finished. Finally, you need to create the filesystem on that disk using [newfs\(8\)](#).

```
# newfs sd2a
```

Or whatever your disk was named as per OpenBSD's disk numbering scheme. (Look at the output from [dmesg\(8\)](#) to see what your disk was named by OpenBSD.)

Now figure out where you are going to mount this new partition you just created. Say you want to put it on /u. First, make the directory /u. Then, mount it.

```
# mount /dev/sd2a /u
```

Finally, add it to [/etc/fstab\(5\)](#).

```
/dev/sd2a /u ffs rw 1 1
```

What if you need to migrate an existing directory like /usr/local? You should mount the new drive in /mnt and use `cpio -pdm` to copy /usr/local to the /mnt directory. Edit the [/etc/fstab\(5\)](#) file to show that the /usr/local partition is now /dev/sd2a (your freshly formatted partition.) Example:

```
/dev/sd2a /usr/local ffs rw 1 1
```

Reboot into single user mode with `boot -s`, move the existing /usr/local to /usr/local-backup (or delete it if you feel lucky) and create an empty directory /usr/local. Then reboot the system, and voila, the files are there!

## 14.4 - How to swap to a file

(Note: if you are looking to swap to a file because you are getting "virtual memory exhausted" errors, you should try raising the per-process limits first with `csch's unlimit\(1\)`, or `sh's ulimit\(1\)`.)

Swapping to a file doesn't require a custom built kernel, although that can still be done, this faq will show you how to add swap space both ways.

## Swapping to a file.

Swapping to a file is easiest and quickest way to get extra swap space setup. The file must not reside on a filesystem which has SoftUpdates enabled (they are disabled by default). To start out, you can see how much swap you currently have and how much you are using with the [swapctl\(8\)](#) utility. You can do this by using the command:

```
$ swapctl -l
Device      512-blocks      Used      Avail Capacity  Priority
swap_device  65520            8         65512    0%      0
```

This shows the devices currently being used for swapping and their current statistics. In the above example there is only one device named "swap\_device". This is the predefined area on disk that is used for swapping. (Shows up as partition b when viewing disklabels) As you can also see in the above example, that device isn't getting much use at the moment. But for the purposes of this document, we will act as if an extra 32M is needed.

The first step to setting up a file as a swap device is to create the file. It's best to do this with the [dd\(1\)](#) utility. Here is an example of creating the file `/var/swap` that is 32M large.

```
$ sudo dd if=/dev/zero of=/var/swap bs=1k count=32768
32768+0 records in
32768+0 records out
33554432 bytes transferred in 20 secs (1677721 bytes/sec)
```

Once this has been done, we can turn on swapping to that device. Use the following command to turn on swapping to this device

```
$ sudo chmod 600 /var/swap
$ sudo swapctl -a /var/swap
```

Now we need to check to see if it has been correctly added to the list of our swap devices.

```
$ swapctl -l
Device      512-blocks      Used      Avail Capacity  Priority
swap_device  65520            8         65512    0%      0
/var/swap    65536            0         65536    0%      0
Total       131056           8         131048    0%
```

Now that the file is setup and swapping is being done, you need to add a line to your `/etc/fstab` file so that this file is configured on the next boot time also. If this line is not added, you won't have this swap device configured.

```
$ cat /etc/fstab
/dev/wd0a / ffs rw 1 1
/var/swap /var/swap swap sw 0 0
```

## Swapping via a vnode device

This is a more permanent solution to adding more swap space. To swap to a file permanently, first make a kernel with `vnd0c` as swap. If you have `wd0a` as root filesystem, `wd0b` is the previous swap, use this line in the kernel configuration file (refer to compiling a new kernel if in doubt):

```
config          bsd          root on wd0a swap on wd0b and vnd0c dumps on wd0b
```

After this is done, the file which will be used for swapping needs to be created. You should do this by using the same command as in the above examples.

```
$ sudo dd if=/dev/zero of=/var/swap bs=1k count=32768
32768+0 records in
32768+0 records out
33554432 bytes transferred in 20 secs (1677721 bytes/sec)
```

Now your file is in place, you need to add the file to you `/etc/fstab`. Here is a sample line to boot with this device as swap on boot.

```
$ cat /etc/fstab
```

```
/dev/wd0a / ffs rw 1 1
/dev/vnd0c none swap sw 0 0
```

At this point your computer needs to be rebooted so that the kernel changes can take place. Once this has been done it's time to configure the device as swap. To do this you will use [vnconfig\(8\)](#).

```
$ sudo vnconfig -c -v vnd0 /var/swap
vnd0: 33554432 bytes on /var/swap
```

Now for the last step, turning on swapping to that device. We will do this just like in the above examples, using [swapctl\(8\)](#). Then we will check to see if it was correctly added to our list of swap devices.

```
$ sudo swapctl -a /dev/vnd0c
$ swapctl -l
Device      512-blocks      Used      Avail Capacity  Priority
swap_device  65520           8        65512    0%      0
/dev/vnd0c   65536           0        65536    0%      0
Total       131056          8        131048   0%
```

## 14.5 - Soft Updates

Soft Updates is based on an idea proposed by [Greg Ganger and Yale Patt](#) and developed for FreeBSD by [Kirk McKusick](#). SoftUpdates imposes a partial ordering on the buffer cache operations which permits the requirement for synchronous writing of directory entries to be removed from the FFS code. Thus, a large performance increase is seen in disk writing performance.

The potential of background [fsck\(8\)](#), using Soft Updates is not yet realised in OpenBSD, so [fsck\(8\)](#) is still required after an unclean shutdown. This may be changed in future versions.

To use Soft Updates, your kernel must have

### option FFS\_SOFTUPDATES

compiled in, this is already in place on GENERIC.

Enabling soft updates must be done with a mount-time option. When mounting a partition with the [mount\(8\)](#) utility, you can specify that you wish to have soft updates enabled on that partition. Below is a sample [/etc/fstab\(5\)](#) entry that has one partition *sd0a* that we wish to have mounted with soft updates.

```
/dev/sd0a / ffs rw,softdep 1 1
```

Note to sparc users: Do not enable soft updates on sun4 or sun4c machines. These architectures support only a very limited amount of kernel memory and cannot use this feature. However, sun4m machines are fine.

## 14.7 - What are the issues regarding large drives with OpenBSD?

OpenBSD has support for file systems of sizes much larger than any currently or soon to be available hard disks, however there are limitations on some interfaces which are smaller than the theoretical maximum of OpenBSD. In the case of IDE drives, the limit is 128GB, the limit of the currently popular ATA interface. Note the next generation of ATA drives, those with capacities greater than 128G (1G=2<sup>30</sup> here, not 1,000,000,000, so drive manufacturers will often call this 137G), are not supported by OpenBSD 3.1 and earlier.

Unfortunately, the full ability of the OS isn't available until AFTER the OS has been loaded into memory, and the booting process introduces limits of its own. The boot process has to utilize (and is thus limited by) the system's boot ROM. The OpenBSD i386 boot loaders ([biosboot\(8\)](#) and [boot\(8\)](#)) also have their own internal 8G limitation, from an older BIOS limit.

For this reason, the entire */bsd* file (the kernel) must be located on the disk within the boot ROM addressable area, or within the first 8G of the disk, whichever is smaller. This means that on some older i386 systems, the root partition must be completely within the first 504M, but for most newer computers, the root partition may be anywhere within the first 8G.

Note that it is possible to install a 40G drive on an old 486 and load OpenBSD on it as one huge partition, and think you have successfully violated the above rule. However, it might come back to haunt you in a most unpleasant way:

- You install on the 40G / partition. It works, because the base OS and all its files (including /bsd) are within the first 504M.
- You use the system, and end up with more than 504M of files on it.
- You upgrade, build your own kernel, whatever, and copy your new /bsd over the old one.
- You reboot.
- You get a message such as "bad magic"

Why? Because when you copied "over" the new /bsd file, it didn't overwrite the old one, it got relocated to a new location on the disk, probably outside the 504M range the BIOS supported. The boot loader was unable to fetch the file /bsd, and the system hung.

To get OpenBSD to boot, /bsd must be within the boot ROM's supported range. To play it safe, the rule is simple:

**The entire root partition must be within the computer's BIOS (or boot ROM) addressable space or within the first 8G, whichever is smaller.** There are no ways around this at this time. Trust us. You *must* follow this rule.

This is another good reason to [partition your hard disk](#), rather than using one large partition.

## 14.8 - Installing Bootblocks - i386 specific

Older versions of MS-DOS can only deal with disk geometries of 1024 cylinders or less. Since virtually all modern disks have more than 1024 cylinders, most SCSI BIOS chips (which come on the SCSI controller card) and IDE BIOS (which is part of the rest of the PC BIOS) have an option (sometimes the default) to "translate" the real disk geometry into something that fits within MS-DOS' ability. However, not all BIOS chips "translate" the geometry in the same way. If you change your BIOS (either with a new motherboard or a new SCSI controller), and the new one uses a different "translated" geometry, you will be unable to load the second stage boot loader (and thus unable to load the kernel). (This is because the first stage boot loader contains a list of the blocks that comprise /boot in terms of the original "translated" geometry). If you are using IDE disks, and you make changes to your BIOS settings, you can (unknowingly) change its translation also (most IDE BIOS offer 3 different translations). To fix your boot block so that you can boot normally, just put a boot floppy in your drive (or use a bootable CD-ROM) and at the boot prompt, type "b hd0a:/bsd" to force it to boot from the first hard disk (and not the floppy). Your machine should come up normally. You now need to update the first stage boot loader to see the new geometry (and re-write the boot block accordingly). Our example will assume your boot disk is sd0 (but for IDE it would be wd0, etc.):

```
# cd /usr/mdec; ./installboot /boot biosboot sd0
```

If installboot complains that it is unable to read the BIOS geometry, at the boot> prompt you may issue the "machine diskinfo" (or "ma di" for short) command to print the information you need. Feed the "heads" and "secs" values to installboot's -h and -s flags, respectively, so that the modified installboot command is the following:

```
# cd /usr/mdec; ./installboot -h <heads> -s <secs> /boot biosboot sd0
```

If a newer version of bootblocks are required, you will need to compile these yourself. To do so simply:

```
# cd /sys/arch/i386/stand/
# make && make install
# cd /usr/mdec; cp ./boot /boot
# ./installboot /boot biosboot sd0 (or whatever device your hard disk is)
```

## 14.9 - Preparing for disaster: Backing up and Restoring from tape

### Introduction:

If you plan on running what might be called a production server, it is advisable to have some form of backup in the event one of your fixed disk drives fails.

This information will assist you in using the standard [dump\(8\)/restore\(8\)](#) utilities provided with OpenBSD. A more advanced backup utility called "Amanda" is also available for backing up multiple servers to one tape drive. In most environments [dump\(8\)/restore\(8\)](#) is enough. However, if you have a need to backup multiple machines to one tape, Amanda might be worth investigating in the future.

The device examples in this document are for a configuration that uses both SCSI disks and tape. In a production environment, SCSI disks are recommended over IDE due to the way in which they handle bad blocks. That is not to say this information is useless if you are using an IDE disk or other type of tape drive, your device names will simply differ slightly. For example sd0a would be wd0a in an IDE based system.

### Backing up to tape:

Backing up to tape requires knowledge of where your file systems are mounted. You can determine how your filesystems are mounted using the [mount\(8\)](#) command at your shell prompt. You should get output similar to this:

```
# mount
/dev/sd0a on / type ffs (local)
/dev/sd0h on /usr type ffs (local)
```

In this example, the root (/) filesystem resides physically on sd0a which indicates SCSI fixed disk 0, partition a. The /usr filesystem resides on sd0h, which indicates SCSI fixed disk 0, partition h.

Another example of a more advanced mount table might be:

```
# mount
/dev/sd0a on / type ffs (local)
/dev/sd0d on /var type ffs (local)
/dev/sd0e on /home type ffs (local)
/dev/sd0h on /usr type ffs (local)
```

In this more advanced example, the root (/) filesystem resides physically on sd0a. The /var filesystem resides on sd0d, the /home filesystem on sd0e and finally /usr on sd0h.

To backup your machine you will need to feed dump the name of each fixed disk partition. Here is an example of the commands needed to backup the simpler mount table listed above:

```
# /sbin/dump -0au -f /dev/nrst0 /dev/rsd0a
# /sbin/dump -0au -f /dev/nrst0 /dev/rsd0h
# mt -f /dev/rst0 rewind
```

For the more advanced mount table example, you would use something similar to:

```
# /sbin/dump -0au -f /dev/nrst0 /dev/rsd0a
# /sbin/dump -0au -f /dev/nrst0 /dev/rsd0d
# /sbin/dump -0au -f /dev/nrst0 /dev/rsd0e
# /sbin/dump -0au -f /dev/nrst0 /dev/rsd0h
# mt -f /dev/rst0 rewind
```

You can review the [dump\(8\)](#) man page to learn exactly what each command line switch does. Here is a brief description of the parameters used above:

- **0** - Perform a level 0 dump, get everything
- **a** - Attempt to automatically determine tape media length
- **u** - Update the file /etc/dumpdates to indicate when backup was last performed
- **f** - Which tape device to use (/dev/nrst0 in this case)

Finally which partition to backup (/dev/rsd0a, etc)

The [mt\(1\)](#) command is used at the end to rewind the drive. Review the mt man page for more options (such as eject).

If you are unsure of your tape device name, use dmesg to locate it. An example tape drive entry in dmesg might appear similar to:

```
st0 at scsibus0 targ 5 lun 0: <ARCHIVE, Python 28388-XXX, 5.28>
```

You may have noticed that when backing up, the tape drive is accessed as device name "nrst0" instead of the "st0" name that is seen in dmesg. When you access st0 as nrst0 you are accessing the same physical tape drive but telling the drive to not rewind at the end of the job and access the device in raw mode. To back up multiple file systems to a single tape, be sure you use the non-rewind device, if you use a rewind device (rst0) to back up multiple file systems, you'll end up overwriting the prior filesystem with the next one dump tries to write to tape. You can find a more elaborate description of various tape drive devices in the [dump](#) man page.

If you wanted to write a small script called "backup", it might look something like this:

```
echo " Starting Full Backup..."
/sbin/dump -0au -f /dev/nrst0 /dev/rsd0a
/sbin/dump -0au -f /dev/nrst0 /dev/rsd0d
```

```

/sbin/dump -0au -f /dev/nrst0 /dev/rsd0e
/sbin/dump -0au -f /dev/nrst0 /dev/rsd0h
echo
echo -n "  Rewinding Drive, Please wait..."
mt -f /dev/rst0 rewind
echo "Done."
echo

```

If scheduled nightly backups are desired, [cron\(8\)](#) could be used to launch your backup script automatically.

It will also be helpful to document (on a scrap of paper) how large each file system needs to be. You can use `df -h` to determine how much space each partition is currently using. This will be handy when the drive fails and you need to recreate your partition table on the new drive.

Restoring your data will also help reduce fragmentation. To ensure you get all files, the best way of backing up is rebooting your system in single user mode. File systems do not need to be mounted to be backed up. Don't forget to mount root (/) r/w after rebooting in single user mode or your dump will fail when trying to write out dumpdates. Enter `bsd -s` at the `boot>` prompt for single user mode.

## Viewing the contents of a dump tape:

After you've backed up your file systems for the first time, it would be a good idea to briefly test your tape and be sure the data on it is as you expect it should be.

You can use the following example to review a catalog of files on a dump tape:

```
# /sbin/restore -tvs 1 -f /dev/rst0
```

This will cause a list of files that exist on the 1st partition of the dump tape to be listed. Following along from the above examples, 1 would be your root (/) file system.

To see what resides on the 2nd tape partition and send the output to a file, you would use a command similar to:

```
# /sbin/restore -tvs 2 -f /dev/rst0 > /home/me/list.txt
```

If you have a mount table like the simple one, 2 would be /usr, if yours is a more advanced mount table 2 might be /var or another fs. The sequence number matches the order in which the file systems are written to tape.

## Restoring from tape:

The example scenario listed below would be useful if your fixed drive has failed completely. In the event you want to restore a single file from tape, review the restore man page and pay attention to the interactive mode instructions.

If you have prepared properly, replacing a disk and restoring your data from tape can be a very quick process. The standard OpenBSD install/boot floppy already contains the required restore utility as well as the binaries required to partition and make your new drive bootable. In most cases, this floppy and your most recent dump tape is all you'll need to get back up and running.

After physically replacing the failed disk drive, the basic steps to restore your data are as follows:

- Boot from the OpenBSD install/boot floppy. At the menu selection, choose Shell. Write protect and insert your most recent back up tape into the drive.
- Using the [fdisk\(8\)](#) command, create a primary OpenBSD partition on this newly installed drive. Example:

```
# fdisk -e sd0
```

See [fdisk FAQ](#) for more info.

- Using the `disklabel` command, recreate your OpenBSD partition table inside that primary OpenBSD partition you just created with `fdisk`. Example:

```
# disklabel -E sd0
```

(Don't forget swap, see [disklabel FAQ](#) for more info)

- Use the `newfs` command to build a clean file system on each partition you created in the above step. Example:

```
# newfs /dev/rsd0a
```

```
# newfs /dev/rsd0h
```

- Mount your newly prepared root (/) file system on /mnt. Example:

```
# mount /dev/sd0a /mnt
```

- Change into that mounted root file system and start the restore process. Example:

```
# cd /mnt
# restore -rs 1 -f /dev/rst0
```

- You'll want this new disk to be bootable, use the following to write a new MBR to your drive. Example:

```
# fdisk -i sd0
```

- In addition to writing a new MBR to the drive, you will need to install boot blocks to boot from it. The following is a brief example:

```
# cp /usr/mdec/boot /mnt/boot
# /usr/mdec/installboot -v /mnt/boot /usr/mdec/biosboot sd0
```

- Your new root file system on the fixed disk should be ready enough so you can boot it and continue restoring the rest of your file systems. Since your operating system is not complete yet, be sure you boot back up with single user mode. At the shell prompt, issue the following commands to unmount and halt the system:

```
# umount /mnt
# halt
```

- Remove the install/boot floppy from the drive and reboot your system. At the OpenBSD boot> prompt, issue the following command:

```
boot> bsd -s
```

The bsd -s will cause the kernel to be started in single user mode which will only require a root (/) file system.

- Assuming you performed the above steps correctly and nothing has gone wrong you should end up at a prompt asking you for a shell path or press return. Press return to use sh. Next, you'll want to remount root in r/w mode as opposed to read only. Issue the following command:

```
# mount -u -w /
```

- Once you have remounted in r/w mode you can continue restoring your other file systems. Example:

```
(simple mount table)
# mount /dev/sd0h /usr; cd /usr; restore -rs 2 -f /dev/rst0

(more advanced mount table)
# mount /dev/sd0d /var; cd /var; restore -rs 2 -f /dev/rst0
# mount /dev/sd0e /home; cd /home; restore -rs 3 -f /dev/rst0
# mount /dev/sd0h /usr; cd /usr; restore -rs 4 -f /dev/rst0
```

You could use "**restore rvsvf**" instead of just rsf to view names of objects as they are extracted from the dump set.

- Finally after you finish restoring all your other file systems to disk, reboot into multiuser mode. If everything went as planned your system will be back to the state it was in as of your most recent back up tape and ready to use again.

## 14.10 - Mounting disk images in OpenBSD

To mount a disk image (ISO images, disk images created with dd, etc) in OpenBSD you must configure a [vnd\(4\)](#) device. For example, if you have an ISO image located at */tmp/ISO.image*, you would take the following steps to mount the image.

```
# vnconfig svnd0 /tmp/ISO.image
# mount -t cd9660 /dev/svnd0c /mnt
```

Notice that, since this image is a CD image you must specify type of *cd9660* when mounting it. This is true, no matter what type, e.g. you must use type *ffs* when mounting disk images.

To unmount the image use the following commands.

```
# umount /mnt
# vnconfig -u svnd0
```

For more information, refer to the [vnconfig\(8\)](#) man page.

## 14.11 - Help! I'm getting errors with PCIIDE!

PCI IDE DMA is unreliable with many combinations of hardware. Until recently, most "mainstream" operating systems that claimed to support DMA transfers with IDE drives did not ship with that feature active by default.

OpenBSD is aggressive and attempts to use the highest DMA Mode it can configure. This will cause corruption of data transfers in some configurations because of buggy motherboard chipsets, buggy drives, and/or noise on the cables. Luckily, Ultra-DMA modes protect data transfers with a CRC to detect corruption. When the Ultra-DMA CRC fails, OpenBSD will print an error message and try the operation again.

```
wd2a: aborted command, interface CRC error reading fsbn 64 of 64-79
(wd2 bn 127; cn 0 tn 2 sn 1), retrying
```

After failing a couple times, OpenBSD will downgrade to a slower (hopefully more reliable) Ultra-DMA mode. If Ultra-DMA mode 0 is hit, then the drive downgrades to PIO mode.

If OpenBSD does not successfully downgrade, or the process causes your machine to lock hard, please send in a [bug report](#).

## 14.13 - RAID options for OpenBSD

RAID (Redundant Array of Inexpensive Disks) gives an opportunity to use multiple drives to give better performance, capacity and/or redundancy than one can get out of a single drive alone. While a full discussion of the benefits and risks of RAID are outside the scope of this article, there are a couple points that are important to make here:

- RAID has nothing to do with backup.
- By itself, RAID will not eliminate down-time.

If this is new information to you, this is not a good starting point for your exploration of RAID.

### Software Options

OpenBSD includes RAIDframe, a software RAID solution. Documentation for it can be found in the following places:

- [FAQ 11, RAID](#)
- [RAIDframe Homepage](#)
- [man page for raidctl\(8\)](#)
- [man page for raid\(4\)](#)

Starting with OpenBSD 3.1, the root partition can now be directly mirrored by OpenBSD using the "Autoconfiguration" option of RAIDframe. Previous releases of OpenBSD could not have the root partition mirrored this way.

### Hardware Options

Many OpenBSD [platforms](#) include support for various hardware RAID products. The options vary by platform, see the appropriate hardware support page (listed [here](#)).

Another option available for many platforms is one of the many products which make multiple drives act as a single IDE or SCSI drive, and are then plugged into a standard IDE or SCSI adapter. These devices can work on virtually any hardware platform that supports either SCSI or IDE.

Some manufacturers of these products:

- [Arco](#)
- [Accusys](#)
- [Maxtronic](#)
- [Infortrend](#)

(Note: these are just products that OpenBSD users have reported using -- this is not any kind of endorsement, nor is it an exhaustive list.)

## Non-Options

An often asked question on the [mail lists](#) is "Are the Promise or HighPoint IDE RAID controllers supported?". The answer is "No". These cards and chips are not true hardware RAID controllers, but rather BIOS-assisted boot of a software RAID. As OpenBSD already supports software RAID in a hardware-independent way, there isn't much desire among the OpenBSD developers to implement special support for these cards.

[\[FAQ Index\]](#) [\[To Section 12 - Platform-Specific Questions\]](#)



[www@openbsd.org](mailto:www@openbsd.org)

\$OpenBSD: faq14.html,v 1.94 2003/10/26 16:45:11 nick Exp \$